

---

# **LWA352 SNAP2 F-Engine Documentation**

***Release 1.0.0***

**Jack Hickish**

**Apr 11, 2021**



**CONTENTS:**

<b>1</b>	<b>Installation</b>	<b>3</b>
1.1	Get the Source Code . . . . .	3
1.2	Install Prerequisites . . . . .	3
<b>2</b>	<b>Control Interface</b>	<b>5</b>
2.1	Overview . . . . .	5
2.2	SNAP2Engine Python Interface . . . . .	6
2.3	etcd Interface . . . . .	17
<b>3</b>	<b>Indices and tables</b>	<b>21</b>
	<b>Index</b>	<b>23</b>



Contents:



## INSTALLATION

The LWA 352 F-Engine pipeline is available at <https://github.com/realtimeradio/caltech-lwa>. Follow the following instructions to download and install the pipeline.

Specify the build directory by defining the `BUILDDIR` environment variable, eg:

```
export BUILDDIR=~/.src/  
mkdir -p $BUILDDIR
```

### 1.1 Get the Source Code

Clone the repository and its dependencies with:

```
# Clone the main repository  
cd $BUILDDIR  
git clone https://github.com/realtimeradio/caltech-lwa  
# Clone relevant submodules  
cd caltech-lwa  
git submodule init  
git submodule update
```

### 1.2 Install Prerequisites

#### 1.2.1 Firmware Requirements

The LWA-253 F-Engine firmware can be built with the CASPER toolflow, and was designed using the following software stack:

- Ubuntu 18.04.0 LTS (64-bit)
- MATLAB R2019a
- Simulink R2019a
- MATLAB Fixed-Point Designer Toolbox R2019a
- Xilinx Vivado HLx 2019.1.3
- Python 3.6.9

It is *strongly* recommended that the same software versions be used to rebuild the design.





## CONTROL INTERFACE

### 2.1 Overview

A Python class `Snap2Fengine` is provided to encapsulate control of individual blocks in the firmware DSP pipeline. The structure of the software interface aims to mirror the hierarchy of the firmware modules, through the use of multiple `Block` class instances, each of which encapsulates control of a single module in the firmware pipeline.

In testing, and interactive debugging, the `Snap2Fengine` class provides an easy way to probe board status for a SNAP2 board on the local network.

In order to integrate with the larger LWA352 control framework, control and monitoring of multiple F-Engines can also be carried out through the passing of JSON-encoded messages through an `etcd`<sup>1</sup> key-value store. This mechanism, shown in Fig. 2.1, utilizes the Python class `Snap2FengineEtcdClient` to translate commands and responses between the `etcd` format and the underlying `Snap2Fengine` method calls.




Fig. 2.1: The top-level control architecture.

---

<sup>1</sup> See [etcd.io](http://etcd.io)

## 2.2 SNAP2Fengine Python Interface

### 2.2.1 Top-Level Control

```
class lwa_f.snap2_fengine.Snap2Fengine (host, logger=None)
```

```
    configure_output (base_ant, n_chans_per_packet, chans, ips, ports=None, ants=None)
```

### 2.2.2 Timing Control

```
class lwa_f.blocks.sync.Sync (host, name, logger=None)
```

```
    arm_noise ()
```

Arm noise generator resets

```
    arm_sync ()
```

Arm sync pulse generator.

```
    count_ext ()
```

Returns Number of external sync pulses received.

```
    count_int ()
```

Returns Number of internal sync pulses received.

```
    get_error_count ()
```

Returns count of number of sync errors

```
    get_latency ()
```

Returns Number of FPGA clock ticks between sync transmission and reception

```
    get_status ()
```

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

```
    initialize (read_only=False)
```

Initialize this block. Set sync period to 0.

```
    load_telescope_time (tt, software_load=False)
```

Load a new starting value into the telescope time counter on the next sync.

tt (int) : Telescope time to load software\_load (bool) : If True, immediately load via a software trigger

```
    period ()
```

Returns the number of FPGA clock ticks between the last two external sync pulses.

```
    reset_error_count ()
```

Reset internal error counter to 0.

```
    reset_telescope_time ()
```

Reset the telescope time counter to 0 immediately.

```
    sw_sync ()
```

Issue a software sync pulse

**uptime()**

Returns uptime in FPGA clock ticks. Resolution is  $2^{32}$  (21 seconds at 200 MHz)

**wait\_for\_sync()**

Block until a sync has been received.

## 2.2.3 ADC Control

**class** `lwa_f.blocks.adc.Adc` (*host, name, logger=None*)

Instantiate a control interface for an ADC block.

### Parameters

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.

**calibrate** (*use\_ramp=False*)

Compute and set all ADC data lane input delays to their optimal values. After this call, the ADCs are left in test mode.

**Parameters** *use\_ramp* (*bool*) – If True, after calibration, use the ramp test pattern to verify the ADC->FPGA link is functioning correctly. If False, perform this verification with the same constant test value used for the calibration procedure.

**Returns** True if the calibration procedure succeeded. False otherwise.

**Return type** *bool*

**get\_snapshot** (*fmc, signed=False, trigger=True*)

Read a snapshot of data from all ADC channels on a single FMC card. Return data without interleaving ADC cores.

### Parameters

- **fmc** (*int*) – Which FMC port (0 or 1) to read.
- **signed** (*bool*) – If True, return data interpreted as signed 2's complement integers. If False, return data as unsigned integers.
- **trigger** (*bool*) – If True, trigger a new simultaneous capture of data from all channels. If False, read existing data capture. Grabbing data without a new trigger may be useful if you wish to read channels from a second FMC port which were captured simultaneously with another port.

**Returns** Array of captured data with dimensions [ADC\_CHIPS\_PER\_FMC, ADC\_LANES, TIME\_SAMPLES]. Data from ADC lanes representing the same analog input are *\_not\_* interleaved. Data from ADC lanes *n,n+1* are associated with the same analog input.

**Return type** *numpy.array*

**get\_snapshot\_interleaved** (*fmc, signed=False, trigger=True*)

Read a snapshot of data from all ADC channels on a single FMC card. Return data with ADC cores interleaved.

### Parameters

- **fmc** (*int*) – Which FMC port (0 or 1) to read.

- **signed** (*bool*) – If True, return data interpreted as signed 2's complement integers. If False, return data as unsigned integers.
- **trigger** (*bool*) – If True, trigger a new simultaneous capture of data from all channels. If False, read existing data capture. Grabbing data without a new trigger may be useful if you wish to read channels from a second FMC port which were captured simultaneously with another port.

**Returns** numpy array of captured data with dimensions [ADC\_CHANNELS\_PER\_FMC, TIME\_SAMPLES].

**Return type** numpy.ndarray

**initialize** (*read\_only=False, clocksource=1*)

Initialize connected ADC boards.

#### Parameters

- **read\_only** (*bool*) – If True, don't do anything which would affect a running system. If False, train ADC->FPGA data links.
- **clocksource** (*int*) – Which ADC board (0 or 1) on an FMC card should serve as the source of the clocks. Note that while this parameter is set for boards on all FMC cards, only the FMC card selected as the clock source at Simulink compile-time will be used for clocking.

**Returns** True if initialization was successful. False otherwise.

**mmcm\_is\_locked** ()

Read the ADC control register to determine if the clock PLLs are locked.

**Returns** True if the ADC clocks are locked. False otherwise.

**Return type** bool

**print\_sweep** (*errs, best\_delays=None, step\_size=4*)

Print, using ASCII, the valid data capture eye as a function of delay setting. Delays are printed such that one row represents a sweep of delays for a single ADC data lane. Each column in the row is X if data contained errors at this delay, - if no errors were detected at this delay, and |, if this delay is considered the best setting in the sweep range.

#### Parameters

- **errs** (*list*) – Array of error counts with dimensions [DELAY\_TRIALS, ADC\_CHIPS, DATA\_LANES\_PER\_ADC\_CHIP] such as that returned by `_get_errs_by_delay`.
- **best\_delays** (*list*) – Array of best delays, with shape [ADC\_CHIPS, DATA\_LANES\_PER\_ADC\_CHIP], such as that returned by `_get_best_delays`. These delays are marked with an ASCII |.
- **step\_size** (*int*) – Number of IDELAY tap steps between delay trials.

**reset** ()

Toggle the ADC reset input.

**set\_delays** (*adc, delays*)

Set IDELAY tap values for all ADC data lanes on an FMC port.

#### Parameters

- **adc** (*casperfpga.ads5296.AD5296*) – ADS5296 object associated with an FMC ADC interface.

- **delays** (*list*) – Array of delays to load, with shape [ADC\_CHIPS, DATA\_LANES\_PER\_ADC\_CHIP], such as that returned by `_get_best_delays`.

**sync()**

Toggle the ADC sync input.

## 2.2.4 Input Control

**class** `lwa_f.blocks.input.Input` (*host, name, n\_streams=64, n\_bits=10, logger=None*)

**get\_all\_histograms()**

Get histograms for all antpols, summing over all interleaving Input:

antpol (int): Antpol number (zero-indexed)

**Returns:**

**vals, hist** vals (numpy array): histogram bin centers hist (numpy array): histogram data

**get\_bit\_stats()**

Get the mean, RMS, and powers of all ADCs Returns:

means, powers, rmss. Each is a numpy array with one entry per input.

**get\_histogram** (*input, sum\_cores=True*)

Get a histogram for an ADC input. Inputs:

input (int): ADC input from which to get data. sum\_cores (Boolean): If True, compute one histogram from both A & B ADC cores. If False, compute separate histograms.

**Returns:**

**If sum\_cores is True:**

**vals, hist** vals (numpy array): histogram bin centers hist (numpy array): histogram data

**If sum\_cores is False:**

**vals, hist\_a, hist\_b** vals (numpy array): histogram bin centers hist\_a (numpy array): histogram data for “A” cores hist\_b (numpy array): histogram data for “B” cores

**get\_power\_spectra** (*stream, acc\_len=1*)

Perform a software FFT of samples from *antenna*. Accumulate power from *acc\_len* snapshots. Returns power spectrum as numpy array

**get\_status()**

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

**initialize** (*read\_only=False*)

Switch to ADCs. Begin computing stats.

**show\_histogram\_plot()**

A helper method for plotting multiple histograms without importing your own pyplot. eg.

```
    for i in range(Input.n_streams): Input.plot_histogram(i)
    Input.show_histogram_plot()

use_adc (stream=None)
    Switch input to ADC. Inputs:

        stream (int): Which stream to switch. If None, switch all.

use_noise (stream=None)
    Switch input to internal noise source. Inputs:

        stream (int): Which stream to switch. If None, switch all.

use_zero (stream=None)
    Switch input to zeros. Inputs:

        stream (int): Which stream to switch. If None, switch all.
```

## 2.2.5 Noise Generator Control

## 2.2.6 Delay Control

```
class lwa_f.blocks.delay.Delay (host, name, n_streams=64, logger=None)
    Instantiate a control interface for a Delay block.
```

### Parameters

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_streams** (*int*) – Number of independent streams which may be delayed

```
MIN_DELAY = 5
    minimum delay allowed
```

```
get_delay (stream)
    Get the current delay for a given input.
```

**Parameters** **stream** (*int*) – Which ADC input index to query

**Returns** Currently loaded delay, in ADC samples

**Return type** *int*

```
get_max_delay ()
    Query the firmware to get the maximum delay it supports.
```

**Returns** Maximum supported delay, in ADC samples

**Return type** *int*

```
get_status ()
    Get status and error flag dictionaries.
```

Status keys:

- **delay<n>**: Currently loaded delay for ADC input index *n*.
- **max\_delay**: The maximum delay supported by the firmware.

- **min\_delay**: The minimum delay supported by the firmware.

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize all delays.

**Parameters** **read\_only** (*bool*) – If True, do nothing. If False, initialize all delays to the minimum allowed value.

**set\_delay** (*stream, delay*)

Set the delay for a given input stream.

**Parameters**

- **stream** (*int*) – ADC stream index to which delay should be applied.
- **delay** (*int*) – Number of ADC clock cycles delay to load.

## 2.2.7 PFB Control

**class** lwa\_f.blocks.pfb.**Pfb** (*host, name, logger=None*)

**get\_status** ()

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

**initialize** (*read\_only=False*)

Individual blocks should override this method to configure themselves appropriately

**Parameters** **read\_only** (*bool*) – If False, initialize blocks in a way that might change the configuration of running hardware. If True, read runtime info from blocks, but don't change anything.

## 2.2.8 Auto-correlation Control

**class** lwa\_f.blocks.autocorr.**AutoCorr** (*host, name, acc\_len=32768, logger=None, n\_chans=4096, n\_pols=64, n\_parallel\_streams=8, n\_cores=4, use\_mux=True*)

Instantiate a control interface for an Auto-Correlation block.

**Parameters**

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **acc\_len** (*int*) – Accumulation length initialization value, in spectra.

- **n\_chans** (*int*) – Number of frequency channels.
- **n\_pols** (*int*) – Number of individual data streams.
- **n\_parallel\_streams** (*int*) – Number of streams processed by the firmware module in parallel.
- **n\_cores** (*int*) – Number of accumulation cores in firmware design.
- **use\_mux** (*bool*) – If True, only one core is instantiated and a multiplexer is used to switch different inputs into it. If False, multiple cores are instantiated simultaneously in firmware.

**get\_acc\_len** ()

Get the currently loaded accumulation length in units of spectra.

**Returns** Current accumulation length

**Return type** *int*

**get\_new\_spectra** (*core=0*)

Get a new average power spectra.

**Parameters** **core** (*int*) – If using multiplexing, read data for this core. If not using multiplexing, read data from all cores.

**Returns** Float32 array of dimensions [POLARIZATION, FREQUENCY CHANNEL] containing autocorrelations with accumulation length divided out.

**Return type** *numpy.array*

**get\_status** ()

Get status and error flag dictionaries.

Status keys:

- **acc\_len** : Currently loaded accumulation length

**return** (*status\_dict*, *flags\_dict*) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize the block, setting (or reading) the accumulation length.

**Parameters** **read\_only** (*bool*) – If False, set the accumulation length to the value provided when this block was instantiated. If True, use whatever accumulation length is currently loaded.

**plot\_spectra** (*core=0*, *db=True*, *show=True*)

Plot the spectra of all polarizations in a single core, with accumulation length divided out

**Parameters**

- **core** (*int*) – If using multiplexing, read data for this core. If not using multiplexing, read data from all cores.
- **db** (*bool*) – If True, plot  $10\log_{10}(\text{power})$ . Else, plot linear.
- **show** (*bool*) – If True, call matplotlib's *show* after plotting

**Returns** *matplotlib.Figure*



**set\_acc\_len** (*acc\_len*)

Set the number of spectra to accumulate.

**Parameters** **acc\_len** (*int*) – Number of spectra to accumulate

## 2.2.9 Correlation Control

**class** `lwa_f.snap2_fengine.Snap2Fengine` (*host, logger=None*)

**configure\_output** (*base\_ant, n\_chans\_per\_packet, chans, ips, ports=None, ants=None*)

## 2.2.10 Post-FFT Test Vector Control

**class** `lwa_f.blocks.eqtvb.EqTvg` (*host, name, n\_streams=64, n\_chans=4096, logger=None*)

Instantiate a control interface for a post-equalization test vector generator block.

### Parameters

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_streams** (*int*) – Number of independent streams which may be delayed
- **n\_chans** (*int*) – Number of frequency channels.

**get\_status** ()

Get status and error flag dictionaries.

Status keys:

- **tvb\_enabled**: Currently state of test vector generator. True if the generator is enabled, else False.

**return** (*status\_dict, flags\_dict*) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize the block.

**Parameters** **read\_only** (*bool*) – If True, do nothing. If False, load frequency-ramp test vectors, but disable the test vector generator.

**read\_stream\_tvg** (*stream*)

Read the test vector loaded to an ADC stream.

**Parameters** **stream** (*int*) – Index of stream from which test vectors should be read.

**Returns** Test vector array, as loaded to the FPGA in 8-bit unsigned integer representation.

**Return type** `numpy.ndarray`

**tvb\_disable()**

Disable the test vector generator

**tvb\_enable()**

Enable the test vector generator.

**tvb\_is\_enabled()**

Query the current test vector generator state.

**Returns** True if the test vector generator is enabled, else False.

**Return type** bool

**write\_const\_per\_stream()**

Write a constant to all the channels of a stream, with stream *i* taking the value *i*.

**write\_freq\_ramp()**

Write a frequency ramp to the test vector that is repeated for all ADC inputs. Data are wrapped to fit into 8 bits. I.e., the test vector value for channel 257 takes the value 1.

**write\_stream\_tvb**(*stream*, *test\_vector*)

Write a test vector pattern to a single signal stream.

**Parameters**

- **stream**(*int*) – Index of stream to which test vectors should be loaded.
- **test\_vector** (*list or numpy.ndarray*) – *self.n\_chans*-element test vector. Values should be representable in 8-bit unsigned integer format. Data are loaded such that the most-significant 4 bits of the test\_vectors are interpreted as the 2's complement 4-bit real sample data. The least-significant 4 bits of the test vectors are interpreted as the 2's complement 4-bit imaginary sample data.

## 2.2.11 Equalization Control

**class** lwa\_f.blocks.eq.Eq(*host*, *name*, *n\_streams*=64, *n\_coeffs*=512, *logger*=None)

Instantiate a control interface for an Equalization block.

**Parameters**

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_streams** (*int*) – Number of independent streams which may be delayed
- **n\_coeffs** (*int*) – Number of coefficients per input stream. Coefficients are shared among neighbouring frequency channels.

**clip\_count()**

Get the total number of times any samples have clipped, since last sync.

**Returns** Clip count.

**Return type** int

**get\_coeffs**(*stream*)

Get the coefficients currently loaded. Reads the actual coefficients from the board.

**Parameters** **stream** (*int*) – ADC stream index to query.

**Returns** (coeffs, binary\_point). *coeffs* is an array of `self.n_coeffs` integer coefficients currently being applied. *binary\_point* is the position of the binary point by which these integers are scaled on the FPGA.

**Return type** (numpy.ndarray, int)

**get\_status()**

Get status and error flag dictionaries.

Status keys:

- *clip\_count*: Number of clip events in the last sync period.
- *width*: Bit width of coefficients
- *binary\_point*: Binary point position of coefficients
- *coefficients<n>*: The currently loaded, integer-valued coefficients for ADC stream *n*.

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize block.

**Parameters** *read\_only* (*bool*) – If False, set all coefficients to some nominally sane value. Currently, this is 100.0. If True, do nothing.

**set\_coeffs** (*stream, coeffs*)

Set the coefficients for a data stream. Clipping and saturation will be applied before loading.

**Parameters**

- **stream** (*int*) – ADC stream index to which coefficients should be applied.
- **coeffs** (*list or numpy.ndarray*) – Array of coefficients to load. This should be of length `self.n_coeffs`, else an `AssertionError` will be raised.

## 2.2.12 Channel Selection Control

## 2.2.13 Packetization Control

**class** `lwa_f.blocks.packetizer.Packetizer` (*host, name, n\_chans=4096, n\_pols=64, sample\_rate\_mhz=200.0, logger=None*)

The packetizer block allows dynamic definition of packet sizes and contents. In firmware, it is a simple block which allows insertion of header entries and EOFs at any point in the incoming data stream. It is up to the user to configure this block such that it behaves in a reasonable manner – i.e.

- Output data rate does not overflow the downstream Ethernet core
- Packets have a reasonable size
- EOFs and headers are correctly placed.

**get\_packet\_info** (*n\_pkt\_chans, occupation=0.95, chan\_block\_size=8*)

Get the packet boundaries for packets with payload sizes *n\_bytes*.

**n\_pkt\_chans** [int] The number of channels per packet.

**occupation** [float] The maximum allowed throughput capacity of the underlying link. The calculation does not include application or protocol overhead, so must necessarily be  $< 1$ .

**chan\_block\_size** [int] The granularity with which we can start packets. I.e., packets must start on an  $n * \text{chan\_block}$  boundary.

packet\_starts, packet\_payloads, channel\_indices

**packet\_starts** [list of ints] The word indexes where packets start – i.e., where headers should be written. For example, a value [0, 1024, 2048, ...] indicates that headers should be written into underlying brams at addresses 0, 1024, etc.

**packet\_payloads** [list of range()] The range of indices where this packet's payload falls. Eg: [range(1,257), range(1025,1281), range(2049,2305), ... etc] These indices should be marked valid, and the last given an EOF.

**channel\_indices** [list of range()] The range of channel indices this packet will send. Eg: [range(1,129), range(1025,1153), range(2049,2177), ... etc] Channels to be sent should be re-indexed so that they fall into these ranges.

**write\_config** (*packet\_starts, packet\_payloads, channel\_indices, ant\_indices, dest\_ips, dest\_ports, print\_config=False*)

Write the packetizer configuration BRAMs with appropriate entries.

**packet\_starts** [list of ints] Word-indices which are the first entry of a packet and should be populated with headers (see *get\_packet\_info()*)

**packet\_payloads** [list of range(s)] Word-indices which are data payloads, and should be mared as valid (see *get\_packet\_info()*)

**channel\_indices** [list of ints] Header entries for the channel field of each packet to be sent

**ant\_indices** [list of ints] Header entries for the antenna field of each packet to be sent

**dest\_ips** [list of str] IP addresses for each packet to be sent.

**dest\_ports** [list of int] UDP destination ports for each packet to be sent.

**print** [bool] If True, print config for debugging

All parameters should have identical lengths.

## 2.2.14 Ethernet Output Control

**class** `lwa_f.blocks.eth.Eth` (*host, name, logger=None*)

**add\_arp\_entry** (*ip, mac*)

Set a single arp entry.

**get\_status** ()

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

**initialize** (*read\_only=False*)

Individual blocks should override this method to configure themselves appropriately

**Parameters** `read_only` (*bool*) – If False, initialize blocks in a way that might change the configuration of running hardware. If True, read runtime info from blocks, but don't change anything.

**set\_arp\_table** (*macs*)

Set the ARP table with a list of MAC addresses. The list, *macs*, is passed such that the zeroth element is the MAC address of the device with IP XXX.XXX.XXX.0, and element N is the MAC address of the device with IP XXX.XXX.XXX.N

## 2.3 etcd Interface

The `etcd` F-Engine interface provides a mechanism to control multiple SNAP2 boards running F-Engine firmware via the passing of messages through an `etcd` key-value store.

In order to use the `etcd` control interface, a daemon `Snap2FEngineEtcdClient` instance is required to be running on a server with network access to the SNAP2 hardware being controlled.

For an F-Engine running on a SNAP2 *hostname*, there are three relevant `etcd` key paths.

The command key is:

```
/cmd/snap/<hostname>/command
```

Writing messages to this key results in the execution of `Snap2FEngine` command methods.

Each command written to the command key will elicit a response published to the key:

```
/resp/snap/<hostname>/response
```

The response message will indicate the success or failure of the command, and may contain a command-dependent data payload. For example, a spectra, or snapshot of ADC samples.

In addition to the Command/Response control protocol, general telemetry relating to pipeline element `blockname` can be read from the keys beneath the path:

```
/mon/snap/<hostname>/<blockname>
```

Such keys are intended to be continuously updated on a ~1 second time cadence, and contain low data-volume status information. For example, FPGA temperature, ADC RMS, number of transmitted Ethernet packets, and similar.

The Command/Response protocol is designed to be a simple interface to the underlying `Snap2FEngine` control class. It will naturally extend as the control class functionality is expanded.

A simple example of a control client is implemented in the `Snap2FEngineEtcdControl` class, which is used for internal testing.

Commands sent to the command key are JSON-encoded dictionaries, and should have the following fields:

Field	Type	Description
<code>sequence_id</code>	integer	A unique integer associated with this command, used to identify the command's response
<code>timestamp</code>	float	The UNIX time when this command was issued
<code>command</code>	string	Command Name
<code>block</code>	string	Firmware block name to which command applies
<code>kwargs</code>	dictionary	Dictionary of arguments required by the <code>block.command</code> method

Allowed values for `block` are any of the keys in the `Snap2FEngine` `blocks` attribute. I.e.:

```
from lwa_f import snap2_fengine
f = snap2_fengine.Snap2Fengine('snap2-rev2-11')
for block in sorted(f.blocks.keys()): print(block)
adc
autocorr
corr
delay
eq
eq_tvg
eth
input
noise
packetizer
pfb
reorder
sync
```

Allowed values for ``command`` are any of the methods which can be called against `Snap2Fengine.blocks[block]`. For example, for the `delay` block, allowed commands are:

- `get_max_delay`
- `set_delay`
- `get_delay`
- `initialize`
- `get_status`

All blocks are instances of the generic `Block` class, and thus it is also possible to call parent class methods such as `read_uint` and `write_uint`. These directly manipulate FPGA registers, and should be used with caution.

The ``kwargs`` field should contain any arguments required by the command method being called. For example, the `Fengine delay` block's `set_delay` method requires a `stream` argument (to select which of the 64 SNAP2 data streams is being manipulated) and a `delay` argument (to set the delay for this stream).

As such, in order to set the delay of data stream 5 to 100 adc samples, a command should be issued with:

Field	Value
block	"delay"
command	"set_delay"
kwargs	{"stream": 5, "delay": 100}

An example of a valid command JSON string, issued with the above parameters at UNIX time 1618060712.60 and with `sequence_id=1` is:

```
'{"block": "delay", "timestamp": 1618060712.6, "kwargs": {"delay": 100, "stream": 5}, "command": "set_delay", "sequence_id": 1}'
```

Consult the `Snap2Fengine` API details for a list of commands and their arguments.

Every command sent elicits the writing of JSON-encoded dictionary to the response key. This dictionary has the following fields:

Field	Type	Description
sequence_id	integer	An integer matching the <code>sequence_id</code> field of the command string to which this is a response
timestamp	float	The UNIX time when this response was issued
status	string	The string “normal” if the corresponding command was processed without error, or “error” if it was not.
response	command dependent	The response of the command method, as determined by the command API. If a method would usually return a numpy array, when using the <code>etcd</code> interface the response will be a list. In the event that the status field is “error”, The response field will contain an error message string

Not all `Snap2FEngine` methods return values, in which case the response field is `null`. The previous command example (setting a delay) results in the underlying API call `Snap2FEngine.blocks['delay'].set_delay(5, 100)` which returns `None`. The response to the example command (assuming processing the command took 0.2 milliseconds) is thus:

Field	Value
sequence_id	1
timestamp	1618060712.8
status	“normal”
response	null

or, in JSON-encoded form:

```
{“sequence_id”: 1, “timestamp”: 1618060712.8, “status”: “normal”,
“response”: null}
```

If the response `status` field is “error”, common response error messages, and their meanings are:

“JSON decode error”	Command string could not be JSON-decoded.
“Sequence ID not integer”	Sequence ID was not provided in the command string or decoded to a non-integer value.
“Bad command format”	Received command did not comply with formatting specifications. E.g. was missing a required field such as <code>block</code> or <code>command</code> .
“Command invalid”	Received command doesn’t exist in the <code>Snap2FEngine</code> API, or is prohibited for <code>etcd</code> access.
“Wrong block”	<code>block</code> field of the command decoded to a block which doesn’t exist.
“Command arguments invalid”	<code>kwargs</code> key contained missing, or unexpected keys.
“Command failed”	The underlying <code>Snap2FEngine</code> API call raised an exception.

In the event that a command fails, more information is available in the `Snap2FEngineEtcdClient` daemon logs.

autocorr/acc_len	int	Accumulation length, in spectra, of the internal autocorrelation module.
corr/acc_len	int	Accumulation length, in spectra, of the internal correlation module.
delay/n/delay	int	Delay of each of the <code>n</code> data streams.
delay/maxdelay	int	The maximum delay supported by the firmware.
eq/binary_point	int	The position of the EQ coefficient binary point
eq/width	int	The bit width of the EQ coefficients
eq/clip_count	int	The number of clips when requantizing spectra to 4-bit. This counter resets every [TODO: w

Table 2.1 – continued from previous page

autocorr/acc_len	int	Accumulation length, in spectra, of the internal autocorrelation module.
eq/n/coefficients	list (int)	The currently loaded coefficients, in integer form (i.e., interpreted with all bits above the bin
eq_tvlg/tvg_enabled	bool	True if the post-FFT test vector generator is enabled. False otherwise.
eth/tx_ctr	int	Running count of number of packets transmitted.
eth/tx_err	int	Running count of number of packet errors detected.
eth/tx_full	int	Running count of number of transmission buffer overflow events.
eth/tx_vld	int	Running count of number of 256-bit words transmitted.
feng/flash_firmware	string	The current .fpg bitstream file stored in flash memory
feng/flash_firmware_md5	int	The MD5 checksum of the .fpg bitstream stored in flash
feng/host	string	The hostname of the SNAP2 board
feng/programmed	bool	True if the board appears to be running DSP firmware. False otherwise.
feng/serial	string	A notional “serial number” of this hardware. Not yet implemented.
feng/sw_version	string	The software version of the <code>lwa_f</code> python library currently in use
feng/sys_mon	string	“reporting” if the current firmware has a working system monitor module. “not reporting” if
feng/temp	float	FPGA junction temperature, in degrees C, reported by system monitor (if available)
feng/vccaux	float	Voltage of the VCCAUX FPGA power rail reported by system monitor (if available)
feng/vccbram	float	Voltage of the VCCBRAM FPGA power rail reported by system monitor (if available)
feng/vccint	float	Voltage of the VCCINT FPGA power rail reported by system monitor (if available)
input/n/mean	float	Mean of ADC sample values for input ADC <i>n</i> .
input/n/rms	float	RMS of ADC sample values for input ADC <i>n</i> .
input/n/power	float	Mean of squares of ADC sample values for input ADC <i>n</i> .
input/n/switch_position	string	Switch position for input data stream <i>n</i> . <code>noise</code> for internal noise generators, <code>adc</code> for analog
noise/noise_core00_seed	int	Seed value for internal noise generator 0.
noise/noise_core01_seed	int	Seed value for internal noise generator 1.
noise/noise_core02_seed	int	Seed value for internal noise generator 2.
noise/n/output_assignment	int	Noise source (0 - 5) currently assigned to data stream <i>n</i> .
pfb/fft_shift	int	Currently loaded FFT shift schedule.
pfb/overflow_count	int	Running count of FFT overflow events.
sync/ext_count	int	Running count of number of external sync pulses received since FPGA was programmed.
sync/int_count	int	Running count of number of internal sync pulses received since FPGA was programmed.
sync/period_fpga_clks	int	Detected period of external sync pulses in units of FPGA clock cycles.
sync/uptime_secs	int	Number of seconds since FPGA was last programmed



## INDICES AND TABLES

- `genindex`
- `modindex`
- `search`



## A

Adc (class in *lwa\_f.blocks.adc*), 7  
 add\_arp\_entry() (*lwa\_f.blocks.eth.Eth* method), 16  
 arm\_noise() (*lwa\_f.blocks.sync.Sync* method), 6  
 arm\_sync() (*lwa\_f.blocks.sync.Sync* method), 6  
 AutoCorr (class in *lwa\_f.blocks.autocorr*), 11

## C

calibrate() (*lwa\_f.blocks.adc.Adc* method), 7  
 clip\_count() (*lwa\_f.blocks.eq.Eq* method), 14  
 configure\_output() (*lwa\_f.snap2\_fengine.Snap2Fengine* method), 6, 13  
 count\_ext() (*lwa\_f.blocks.sync.Sync* method), 6  
 count\_int() (*lwa\_f.blocks.sync.Sync* method), 6

## D

Delay (class in *lwa\_f.blocks.delay*), 10

## E

Eq (class in *lwa\_f.blocks.eq*), 14  
 EqTvg (class in *lwa\_f.blocks.eqtvg*), 13  
 Eth (class in *lwa\_f.blocks.eth*), 16

## G

get\_acc\_len() (*lwa\_f.blocks.autocorr.AutoCorr* method), 12  
 get\_all\_histograms() (*lwa\_f.blocks.input.Input* method), 9  
 get\_bit\_stats() (*lwa\_f.blocks.input.Input* method), 9  
 get\_coeffs() (*lwa\_f.blocks.eq.Eq* method), 14  
 get\_delay() (*lwa\_f.blocks.delay.Delay* method), 10  
 get\_error\_count() (*lwa\_f.blocks.sync.Sync* method), 6  
 get\_histogram() (*lwa\_f.blocks.input.Input* method), 9  
 get\_latency() (*lwa\_f.blocks.sync.Sync* method), 6  
 get\_max\_delay() (*lwa\_f.blocks.delay.Delay* method), 10

get\_new\_spectra() (*lwa\_f.blocks.autocorr.AutoCorr* method), 12  
 get\_packet\_info() (*lwa\_f.blocks.packetizer.Packetizer* method), 15  
 get\_power\_spectra() (*lwa\_f.blocks.input.Input* method), 9  
 get\_snapshot() (*lwa\_f.blocks.adc.Adc* method), 7  
 get\_snapshot\_interleaved() (*lwa\_f.blocks.adc.Adc* method), 7  
 get\_status() (*lwa\_f.blocks.autocorr.AutoCorr* method), 12  
 get\_status() (*lwa\_f.blocks.delay.Delay* method), 10  
 get\_status() (*lwa\_f.blocks.eq.Eq* method), 15  
 get\_status() (*lwa\_f.blocks.eqtvg.EqTvg* method), 13  
 get\_status() (*lwa\_f.blocks.eth.Eth* method), 16  
 get\_status() (*lwa\_f.blocks.input.Input* method), 9  
 get\_status() (*lwa\_f.blocks.pfb.Pfb* method), 11  
 get\_status() (*lwa\_f.blocks.sync.Sync* method), 6

## I

initialize() (*lwa\_f.blocks.adc.Adc* method), 8  
 initialize() (*lwa\_f.blocks.autocorr.AutoCorr* method), 12  
 initialize() (*lwa\_f.blocks.delay.Delay* method), 11  
 initialize() (*lwa\_f.blocks.eq.Eq* method), 15  
 initialize() (*lwa\_f.blocks.eqtvg.EqTvg* method), 13  
 initialize() (*lwa\_f.blocks.eth.Eth* method), 16  
 initialize() (*lwa\_f.blocks.input.Input* method), 9  
 initialize() (*lwa\_f.blocks.pfb.Pfb* method), 11  
 initialize() (*lwa\_f.blocks.sync.Sync* method), 6  
 Input (class in *lwa\_f.blocks.input*), 9

## L

load\_telescope\_time() (*lwa\_f.blocks.sync.Sync* method), 6

## M

MIN\_DELAY (*lwa\_f.blocks.delay.Delay* attribute), 10  
 mmcm\_is\_locked() (*lwa\_f.blocks.adc.Adc* method), 8

## P

Packetizer (*class in lwa\_f.blocks.packetizer*), 15  
period() (*lwa\_f.blocks.sync.Sync method*), 6  
Pfb (*class in lwa\_f.blocks.pfb*), 11  
plot\_spectra() (*lwa\_f.blocks.autocorr.AutoCorr method*), 12  
print\_sweep() (*lwa\_f.blocks.adc.Adc method*), 8

## R

read\_stream\_tvg() (*lwa\_f.blocks.eqtvq.EqTvg method*), 13  
reset() (*lwa\_f.blocks.adc.Adc method*), 8  
reset\_error\_count() (*lwa\_f.blocks.sync.Sync method*), 6  
reset\_telescope\_time() (*lwa\_f.blocks.sync.Sync method*), 6

## S

set\_acc\_len() (*lwa\_f.blocks.autocorr.AutoCorr method*), 12  
set\_arp\_table() (*lwa\_f.blocks.eth.Eth method*), 17  
set\_coeffs() (*lwa\_f.blocks.eq.Eq method*), 15  
set\_delay() (*lwa\_f.blocks.delay.Delay method*), 11  
set\_delays() (*lwa\_f.blocks.adc.Adc method*), 8  
show\_histogram\_plot() (*lwa\_f.blocks.input.Input method*), 9  
Snap2FEngine (*class in lwa\_f.snap2\_fengine*), 6, 13  
sw\_sync() (*lwa\_f.blocks.sync.Sync method*), 6  
Sync (*class in lwa\_f.blocks.sync*), 6  
sync() (*lwa\_f.blocks.adc.Adc method*), 9

## T

tvq\_disable() (*lwa\_f.blocks.eqtvq.EqTvg method*), 13  
tvq\_enable() (*lwa\_f.blocks.eqtvq.EqTvg method*), 14  
tvq\_is\_enabled() (*lwa\_f.blocks.eqtvq.EqTvg method*), 14

## U

uptime() (*lwa\_f.blocks.sync.Sync method*), 6  
use\_adc() (*lwa\_f.blocks.input.Input method*), 10  
use\_noise() (*lwa\_f.blocks.input.Input method*), 10  
use\_zero() (*lwa\_f.blocks.input.Input method*), 10

## W

wait\_for\_sync() (*lwa\_f.blocks.sync.Sync method*), 7  
write\_config() (*lwa\_f.blocks.packetizer.Packetizer method*), 16  
write\_const\_per\_stream() (*lwa\_f.blocks.eqtvq.EqTvg method*), 14  
write\_freq\_ramp() (*lwa\_f.blocks.eqtvq.EqTvg method*), 14

write\_stream\_tvg() (*lwa\_f.blocks.eqtvq.EqTvg method*), 14