

---

# **LWA352 SNAP2 F-Engine Documentation**

***Release 1.0.0***

**Jack Hickish**

**Apr 20, 2021**



**CONTENTS:**

<b>1</b>	<b>Installation</b>	<b>3</b>
1.1	Get the Source Code . . . . .	3
1.2	Install Prerequisites . . . . .	3
<b>2</b>	<b>Control Interface</b>	<b>5</b>
2.1	Overview . . . . .	5
2.2	SNAP2Engine Python Interface . . . . .	6
2.3	etcd Interface . . . . .	24
<b>3</b>	<b>F-Engine Register Definitions</b>	<b>29</b>
3.1	Register Descriptions . . . . .	29
<b>4</b>	<b>Indices and tables</b>	<b>35</b>
	<b>Index</b>	<b>37</b>



Contents:



## INSTALLATION

The LWA 352 F-Engine pipeline is available at <https://github.com/realtimeradio/caltech-lwa>. Follow the following instructions to download and install the pipeline.

Specify the build directory by defining the `BUILDDIR` environment variable, eg:

```
export BUILDDIR=~/.src/  
mkdir -p $BUILDDIR
```

### 1.1 Get the Source Code

Clone the repository and its dependencies with:

```
# Clone the main repository  
cd $BUILDDIR  
git clone https://github.com/realtimeradio/caltech-lwa  
# Clone relevant submodules  
cd caltech-lwa  
git submodule init  
git submodule update
```

### 1.2 Install Prerequisites

#### 1.2.1 Firmware Requirements

The LWA-253 F-Engine firmware can be built with the CASPER toolflow, and was designed using the following software stack:

- Ubuntu 18.04.0 LTS (64-bit)
- MATLAB R2019a
- Simulink R2019a
- MATLAB Fixed-Point Designer Toolbox R2019a
- Xilinx Vivado HLx 2019.1.3
- Python 3.6.9

It is *strongly* recommended that the same software versions be used to rebuild the design.





## CONTROL INTERFACE

### 2.1 Overview

A Python class `Snap2Fengine` is provided to encapsulate control of individual blocks in the firmware DSP pipeline. The structure of the software interface aims to mirror the hierarchy of the firmware modules, through the use of multiple `Block` class instances, each of which encapsulates control of a single module in the firmware pipeline.

In testing, and interactive debugging, the `Snap2Fengine` class provides an easy way to probe board status for a SNAP2 board on the local network.

In order to integrate with the larger LWA352 control framework, control and monitoring of multiple F-Engines can also be carried out through the passing of JSON-encoded messages through an `etcd`<sup>1</sup> key-value store. This mechanism, shown in Fig. 2.1, utilizes the Python class `Snap2FengineEtcdClient` to translate commands and responses between the `etcd` format and the underlying `Snap2Fengine` method calls.




Fig. 2.1: The top-level control architecture.

---

<sup>1</sup> See [etcd.io](http://etcd.io)

## 2.2 SNAP2Fengine Python Interface

### 2.2.1 Top-Level Control

**class** `lwa_f.snap2_fengine.Snap2Fengine` (*host, logger=None*)

A control class for LWA352's SNAP2 F-Engine firmware.

#### Parameters

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.

#### **adc**

Control interface to ADC block

#### **autocorr**

Control interface to Autocorrelation block

#### **blocks**

Dictionary of all control blocks in the firmware system.

**configure\_output** (*base\_ant, n\_chans\_per\_packet, chans, ips, ports=None*)

Configure channel reordering and packetizer modules to emit a selection of frequency channels.

#### Parameters

- **base\_ant** (*int*) – Antenna ID which should be written to output packet headers. In general this should be the first antenna on this F-engine board.
- **n\_chans\_per\_packet** (*int*) – Number of channels per packet.
- **chans** (*list of int*) – A list of channel indices to be sent, e.g. `range(0, 1024)`. The number of channels in this list should be an integer multiple of `n_chans_per_packet`. An assertion error is raised if this is not the case.
- **ips** (*list of str*) – A list of IP addresses to which packets should be sent. The order of values in `ips` and `chans` should reflect where different channels should be sent. The *n*th IP address in `ips` is the destination to which channels `chans[n*n_chans_per_packet : (n+1)*n_chans_per_packet]` should be sent. As such, `ips` should have `len(chans) // n_chans_per_packet` elements. IP addresses should be provided in dotted-quad string representation.
- **ports** (*list of int*) – The UDP destination ports to which packets should be transmitted. Addressing rules are the same as for `ips`. If `None`, all packets are transmitted to UDP port 10000.

#### **corr**

Control interface to Correlation block

#### **delay**

Control interface to Coarse Delay block

#### **eq**

Control interface to Equalization block

#### **eq\_tvg**

Control interface to post-equalization Test Vector Generator block

#### **eth**

Control interface to 40GbE interface block

**fpga**  
Control interface to high-level FPGA functionality

**get\_status\_all()**  
Call the `get_status` methods of all blocks in `self.blocks`.  
  
**Returns** The contents of the underlying `get_status` calls, in a dictionary keyed by the names of the blocks in `self.blocks`.

**hostname**  
hostname of the F-Engine's host SNAP2 board

**initialize(read\_only=True)**  
Call the `initialize` methods of all underlying blocks.  
  
**Parameters** **read\_only** (*bool*) – If True, call the underlying initialization methods in a `read_only` manner.

**input**  
Control interface to Input Multiplex block

**noise**  
Control interface to Noise Generation block

**packetizer**  
Control interface to Packetizer block

**pfb**  
Control interface to PFB block

**print\_status\_all(use\_color=True)**  
Print the status returned by `get_status` for all blocks in the system.  
  
**Parameters** **use\_color** (*bool*) – If True, highlight values with colors based on error codes.

**reorder**  
Control interface to Channel Reorder block

**sync**  
Control interface to Synchronization / Timing block

## 2.2.2 FPGA Control

**class** `lwa_f.blocks.fpga.Fpga` (*host, name, logger=None*)  
Instantiate a control interface for top-level FPGA control.

**Parameters**

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.

**get\_build\_time()**  
Read the UNIX time at which the current firmware was built.  
  
**Return** **build\_time** Seconds since the UNIX epoch at which the running firmware was built.

**Rtype** `int`

**get\_firmware\_version()**  
Read the firmware version register and return the contents as a string.

**Return version** major\_version.minor\_version.revision.bugfix

**Rtype str**

**get\_status()**

Get status and error flag dictionaries.

Status keys:

- **programmed (bool)** : `True` if FPGA appears to be running DSP firmware. `False` otherwise, and flagged as a warning.
- **flash\_firmware (str)** : The name of the firmware file currently loaded in flash memory.
- **flash\_firmware\_md5 (str)** : The MD5 checksum of the firmware file currently loaded in flash memory.
- **timestamp (str)** : The current time, as an ISO format string.
- **serial (str)** : The serial number / identifier for this board. Flagged with a warning if no serial is available.
- **host (str)** : The host name of this board.
- **sw\_version (str)** : The version string of the control software package. Flagged as warning if the version indicates a build against a dirty git repository.
- **fw\_version (str)** : The version string of the currently running firmware. Available only if the board is programmed.
- **fw\_build\_time (int)** : The build time, in seconds since the UNIX epoch. Available only if the board is programmed.
- **sys\_mon (str)** : `'reporting'` if the current firmware has a functioning system monitor module. Otherwise `'not reporting'`, flagged as an error.
- **temp (float)** : FPGA junction temperature, in degrees C. (Only reported is system monitor is available). Flagged as a warning if outside the recommended operating conditions. Flagged as an error if outside the absolute maximum ratings. See DS892.
- **vccaux (float)** : Voltage of the VCCAUX FPGA power rail. (Only reported is system monitor is available). Flagged as a warning if outside the recommended operating conditions. Flagged as an error if outside the absolute maximum ratings. See DS892.
- **vccbram (float)** : Voltage of the VCCBRAM FPGA power rail. (Only reported is system monitor is available). Flagged as a warning if outside the recommended operating conditions. Flagged as an error if outside the absolute maximum ratings. See DS892.
- **vccint (float)** : Voltage of the VCCINT FPGA power rail. (Only reported is system monitor is available). Flagged as a warning if outside the recommended operating conditions. Flagged as an error if outside the absolute maximum ratings. See DS892.

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**is\_programmed()**

Lazy check to see if a board is programmed. Check for the “version\_version” register. If it exists, the board is deemed programmed.

**Returns** `True` if programmed, `False` otherwise.

**Return type** `bool`

## 2.2.3 Timing Control

```
class lwa_f.blocks.sync.Sync(host, name, logger=None)
```

**arm\_noise()**  
Arm noise generator resets

**arm\_sync()**  
Arm sync pulse generator.

**count\_ext()**  
**Returns** Number of external sync pulses received.  
**Rtype** int

**count\_int()**  
**Returns** Number of internal sync pulses received.  
**Rtype** int

**get\_error\_count()**  
**Returns** Number of sync errors.  
**Rtype** int

**get\_latency()**  
**Returns** Number of FPGA clock ticks between sync transmission and reception  
**Rtype** int

**get\_status()**  
Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks  
**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

**initialize(read\_only=False)**  
Initialize block.  
**Parameters** **read\_only** (*bool*) – If False, initialize system control register to 0 and reset error counters. If True, do nothing.

**load\_telescope\_time(tt, software\_load=False)**  
Load a new starting value into the telescope time counter on the next sync.  
**Parameters**

- **tt** (*int*) – Telescope time to load
- **software\_load** (*bool*) – If True, immediately load via a software trigger. Else load on the next external sync pulse arrival.

**period()**  
**Returns** The number of FPGA clock ticks between the last two external sync pulses.  
**Rtype** int

**reset\_error\_count()**  
Reset internal error counter to 0.

**reset\_telescope\_time()**

Reset the telescope time counter to 0 immediately.

**sw\_sync()**

Issue a software sync pulse

**uptime()**

**Returns** Time in FPGA clock ticks since the FPGA was last programmed. Resolution is  $2^{32}$  (21 seconds at 200 MHz)

**Return type** `int`

**wait\_for\_sync()**

Block until a sync has been received.

## 2.2.4 ADC Control

**class** `lwa_f.blocks.adc.Adc` (*host, name, logger=None*)

Instantiate a control interface for an ADC block.

### Parameters

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.

**calibrate** (*use\_ramp=False*)

Compute and set all ADC data lane input delays to their optimal values. After this call, the ADCs are left in test mode.

**Parameters** **use\_ramp** (*bool*) – If True, after calibration, use the ramp test pattern to verify the ADC->FPGA link is functioning correctly. If False, perform this verification with the same constant test value used for the calibration procedure.

**Returns** True if the calibration procedure succeeded. False otherwise.

**Return type** `bool`

**get\_snapshot** (*fmc, signed=False, trigger=True*)

Read a snapshot of data from all ADC channels on a single FMC card. Return data without interleaving ADC cores.

### Parameters

- **fmc** (*int*) – Which FMC port (0 or 1) to read.
- **signed** (*bool*) – If True, return data interpreted as signed 2's complement integers. If False, return data as unsigned integers.
- **trigger** (*bool*) – If True, trigger a new simultaneous capture of data from all channels. If False, read existing data capture. Grabbing data without a new trigger may be useful if you wish to read channels from a second FMC port which were captured simultaneously with another port.

**Returns** Array of captured data with dimensions [ADC\_CHIPS\_PER\_FMC, ADC\_LANES, TIME\_SAMPLES]. Data from ADC lanes representing the same analog input are `_not_` interleaved. Data from ADC lanes `n,n+1` are associated with the same analog input.

**Return type** `numpy.array`

**get\_snapshot\_interleaved** (*fmc*, *signed=False*, *trigger=True*)

Read a snapshot of data from all ADC channels on a single FMC card. Return data with ADC cores interleaved.

#### Parameters

- **fmc** (*int*) – Which FMC port (0 or 1) to read.
- **signed** (*bool*) – If True, return data interpreted as signed 2's complement integers. If False, return data as unsigned integers.
- **trigger** (*bool*) – If True, trigger a new simultaneous capture of data from all channels. If False, read existing data capture. Grabbing data without a new trigger may be useful if you wish to read channels from a second FMC port which were captured simultaneously with another port.

**Returns** numpy array of captured data with dimensions [ADC\_CHANNELS\_PER\_FMC, TIME\_SAMPLES].

**Return type** numpy.ndarray

**initialize** (*read\_only=False*, *clocksource=1*)

Initialize connected ADC boards.

#### Parameters

- **read\_only** (*bool*) – If True, don't do anything which would affect a running system. If False, train ADC->FPGA data links.
- **clocksource** (*int*) – Which ADC board (0 or 1) on an FMC card should serve as the source of the clocks. Note that while this parameter is set for boards on all FMC cards, only the FMC card selected as the clock source at Simulink compile-time will be used for clocking.

**Returns** True if initialization was successful. False otherwise.

**mmcm\_is\_locked** ()

Read the ADC control register to determine if the clock PLLs are locked.

**Returns** True if the ADC clocks are locked. False otherwise.

**Return type** bool

**print\_sweep** (*errs*, *best\_delays=None*, *step\_size=4*)

Print, using ASCII, the valid data capture eye as a function of delay setting. Delays are printed such that one row represents a sweep of delays for a single ADC data lane. Each column in the row is X if data contained errors at this delay, - if no errors were detected at this delay, and |, if this delay is considered the best setting in the sweep range.

#### Parameters

- **errs** (*list*) – Array of error counts with dimensions [DELAY\_TRIALS, ADC\_CHIPS, DATA\_LANES\_PER\_ADC\_CHIP] such as that returned by `_get_errs_by_delay`.
- **best\_delays** (*list*) – Array of best delays, with shape [ADC\_CHIPS, DATA\_LANES\_PER\_ADC\_CHIP], such as that returned by `_get_best_delays`. These delays are marked with an ASCII |.
- **step\_size** (*int*) – Number of IDELAY tap steps between delay trials.

**reset** ()

Toggle the ADC reset input.

**set\_delays** (*adc*, *delays*)

Set IDELAY tap values for all ADC data lanes on an FMC port.

**Parameters**

- **adc** (*casperfpga.ads5296.AD5296*) – ADS5296 object associated with an FMC ADC interface.
- **delays** (*list*) – Array of delays to load, with shape [ADC\_CHIPS, DATA\_LANES\_PER\_ADC\_CHIP], such as that returned by `_get_best_delays`.

**sync** ()

Toggle the ADC sync input.

## 2.2.5 Input Control

**class** `lwa_f.blocks.input.Input` (*host*, *name*, *n\_streams=64*, *n\_bits=10*, *logger=None*)

Instantiate a control interface for an Input block.

**Parameters**

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_streams** (*int*) – Number of independent streams which may be delayed
- **n\_bits** (*int*) – Number of bits per ADC sample.

**get\_all\_histograms** ()

Get histograms for all antpolos, summing over all interleaving cores.

**Returns** (*vals*, *hists*). *vals* is a list of histogram bin centers. *hists* is an [*n\_stream* x 2\*\**n\_bits*] list of histogram data.

**get\_bit\_stats** ()

Get the mean, RMS, and mean powers of all ADC streams.

**Returns** (*means*, *powers*, *rmss*) tuple. Each member of the tuple is an array with *self.n\_streams* elements.

**Rval** (*numpy.ndarray*, *numpy.ndarray*, *numpy.ndarray*)

**get\_histogram** (*stream*, *sum\_cores=True*)

Get a histogram for an ADC stream.

**Parameters**

- **stream** (*int*) – ADC stream from which to get data.
- **sum\_cores** (*bool*) – If True, compute one histogram from both A & B ADC cores. If False, compute separate histograms.

**Returns** If *sum\_cores* is True, return (*vals*, *hist*), where *vals* is a list of histogram bin centers, and *hist* is a list of histogram data points. If *sum\_cores* is False, return (*vals*, *hist\_a*, *hist\_b*), where *hist\_a* and *hist\_b* are separate histogram data sets for the A and B ADC cores, respectively.

**get\_status** ()

Get status and error flag dictionaries.



Status keys:

- `switch_position<n>` (str) : Switch position ('noise', 'adc' or 'zero') for input stream `n`, where `n` is a two-digit integer starting at 00. Any input position other than 'adc' is flagged with "NOTIFY".
- `power<n>` (float) : Mean power of input stream `n`, where `n` is a two-digit integer starting at 00. In units of (ADC LSBs)\*\*2.
- `rms<n>` (float) : RMS of input stream `n`, where `n` is a two-digit integer starting at 00. In units of ADC LSBs. Value is flagged as a warning if it is >30 or <5.
- `mean<n>` (float) : Mean sample value of input stream `n`, where `n` is a two-digit integer starting at 00. In units of ADC LSBs. Value is flagged as a warning if it is > 2.

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**get\_switch\_positions()**

Get the positions of the input switches.

**Returns** List of switch positions. Entry `n` contains the position of the switch associated with ADC input `n`. Switch positions are "noise" (internal digital noise generators), "adc" (digitized ADC stream), or "zero" (constant 0).

**Return type** list of str

**initialize** (*read\_only=False*)

Initialize the block.

**Parameters** *read\_only* (*bool*) – If True, do nothing. If False, set the input multiplexers to ADC data and enable statistic computation.

**plot\_histogram** (*stream*)

Plot a histogram.

**Parameters** *stream* (*int*) – ADC stream from which to get data.

**print\_histograms** ()

Print histogram stats to screen.

**use\_adc** (*stream=None*)

Switch input to ADC.

**Parameters** *stream* (*int* or *None*) – Which stream to switch. If None, switch all.

**use\_noise** (*stream=None*)

Switch input to internal noise source.

**Parameters** *stream* (*int* or *None*) – Which stream to switch. If None, switch all.

**use\_zero** (*stream=None*)

Switch input to zeros.

**Parameters** *stream* (*int* or *None*) – Which stream to switch. If None, switch all.

## 2.2.6 Noise Generator Control

**class** `lwa_f.blocks.noisegen.NoiseGen` (*host, name, n\_noise=5, n\_outputs=64, logger=None*)  
Noise Generator controller

This block controls a digital noise source, which can generate multiple independent channels of gaussian noise. These channels can be assigned to multiple outputs of this block, to create correlated or uncorrelated noise streams.

### Parameters

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_noise** (*int*) – The number of independent noise generation cores in the underlying block.  $2 \times n\_noise$  independent noise streams will be produced.
- **n\_outputs** (*int*) – The number of output channels from the block.

**assign\_output** (*output, noise*)

Assign an output channel to a given noise stream. Note that the output stream will not be affected unless the downstream input multiplexors are set to noise mode.

### Parameters

- **output** (*int*) – The index of the output stream to be assigned.
- **noise** (*int*) – The index of the noise stream to assign to *output*. Note that each noise generator core generates two independent streams, so *noise* can be in range(0,  $2 \times \text{self.n\_noise}$ )

**get\_output\_assignment** (*output*)

Get the index of the noise stream assigned to an output.

**Parameters** **output** (*int*) – The index of the output stream to query.

**Returns** The index of the noise stream to assign to *output*. Note that each noise generator core generates two independent streams, so *noise* can be in range(0,  $2 \times \text{self.n\_noise}$ )

**Return type** *int*

**get\_seed** (*n*)

Get the seed of a noise generator.

**Parameters** **n** (*int*) – Noise generator ID whose seed to read.

**Returns** Noise generator seed.

**Rtype** *int*

**get\_status** ()

Get status and error flag dictionaries.

Status keys:

- **noise\_core<m>\_seed** (*int*): Seed currently loaded into noise generator core *m*. *m* should be a two-digit integer starting at 00.
- **output\_assignment<n>** (*int*): The noise generator ID currently assigned to output stream *n*, where *n* is a two-digit integer starting at 00.

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize the block

**Parameters** **read\_only** (*bool*) – If False, set the seen of noise generator *n* to *n*. If True, do nothing.

**set\_seed** (*n, seed*)

Set the seed of a noise generator.

**Parameters**

- **n** (*int*) – Noise generator ID to seed.
- **seed** (*int*) – Noise generator seed to load.

## 2.2.7 Delay Control

**class** `lwa_f.blocks.delay.Delay` (*host, name, n\_streams=64, logger=None*)

Instantiate a control interface for a Delay block.

**Parameters**

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_streams** (*int*) – Number of independent streams which may be delayed

**MIN\_DELAY** = 5

minimum delay allowed

**get\_delay** (*stream*)

Get the current delay for a given input.

**Parameters** **stream** (*int*) – Which ADC input index to query

**Returns** Currently loaded delay, in ADC samples

**Return type** *int*

**get\_max\_delay** ()

Query the firmware to get the maximum delay it supports.

**Returns** Maximum supported delay, in ADC samples

**Return type** *int*

**get\_status** ()

Get status and error flag dictionaries.

Status keys:

- **delay<n>**: Currently loaded delay for ADC input index *n*. in units of ADC samples.
- **max\_delay**: The maximum delay supported by the firmware.
- **min\_delay**: The minimum delay supported by the firmware.

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize all delays.

**Parameters** *read\_only* (*bool*) – If True, do nothing. If False, initialize all delays to the minimum allowed value.

**set\_delay** (*stream, delay*)

Set the delay for a given input stream.

**Parameters**

- **stream** (*int*) – ADC stream index to which delay should be applied.
- **delay** (*int*) – Number of ADC clock cycles delay to load.

## 2.2.8 PFB Control

**class** lwa\_f.blocks.pfb.**Pfb** (*host, name, logger=None*)

**get\_status** ()

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

**initialize** (*read\_only=False*)

Individual blocks should override this method to configure themselves appropriately

**Parameters** *read\_only* (*bool*) – If False, initialize blocks in a way that might change the configuration of running hardware. If True, read runtime info from blocks, but don't change anything.

## 2.2.9 Auto-correlation Control

**class** lwa\_f.blocks.autocorr.**AutoCorr** (*host, name, acc\_len=32768, logger=None, n\_chans=4096, n\_pols=64, n\_parallel\_streams=8, n\_cores=4, use\_mux=True*)

Instantiate a control interface for an Auto-Correlation block.

**Parameters**

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **acc\_len** (*int*) – Accumulation length initialization value, in spectra.
- **n\_chans** (*int*) – Number of frequency channels.

- **n\_pols** (*int*) – Number of individual data streams.
- **n\_parallel\_streams** (*int*) – Number of streams processed by the firmware module in parallel.
- **n\_cores** (*int*) – Number of accumulation cores in firmware design.
- **use\_mux** (*bool*) – If True, only one core is instantiated and a multiplexer is used to switch different inputs into it. If False, multiple cores are instantiated simultaneously in firmware.

**get\_acc\_len** ()

Get the currently loaded accumulation length in units of spectra.

**Returns** Current accumulation length

**Return type** *int*

**get\_new\_spectra** (*core=0*)

Get a new average power spectra.

**Parameters** **core** (*int*) – If using multiplexing, read data for this core. If not using multiplexing, read data from all cores.

**Returns** Float32 array of dimensions [POLARIZATION, FREQUENCY CHANNEL] containing autocorrelations with accumulation length divided out.

**Return type** *numpy.array*

**get\_status** ()

Get status and error flag dictionaries.

Status keys:

- **acc\_len** (*int*) : Currently loaded accumulation length in number of spectra.

**Returns** (*status\_dict*, *flags\_dict*) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize the block, setting (or reading) the accumulation length.

**Parameters** **read\_only** (*bool*) – If False, set the accumulation length to the value provided when this block was instantiated. If True, use whatever accumulation length is currently loaded.

**plot\_spectra** (*core=0, db=True, show=True*)

Plot the spectra of all polarizations in a single core, with accumulation length divided out

**Parameters**

- **core** (*int*) – If using multiplexing, read data for this core. If not using multiplexing, read data from all cores.
- **db** (*bool*) – If True, plot  $10\log_{10}(\text{power})$ . Else, plot linear.
- **show** (*bool*) – If True, call matplotlib's *show* after plotting

**Returns** *matplotlib.Figure*

**set\_acc\_len** (*acc\_len*)

Set the number of spectra to accumulate.

**Parameters** **acc\_len** (*int*) – Number of spectra to accumulate

## 2.2.10 Correlation Control

**class** `lwa_f.blocks.corr.Corr` (*host, name, acc\_len=1024, logger=None, n\_chans=1024*)

Instantiate a control interface for a Correlation block.

### Parameters

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **acc\_len** (*int*) – Accumulation length initialization value, in spectra.
- **n\_chans** (*int*) – Number of frequency channels in the correlation output.

**get\_acc\_len** ()

Get the currently loaded accumulation length in units of spectra.

**Returns** Current accumulation length

**Return type** `int`

**get\_new\_corr** (*pol1, pol2, flush\_vacc=True*)

Get a new correlation.

### Parameters

- **pol1** (*int*) – First (unconjugated) polarization index.
- **pol2** (*int*) – Second (conjugated) polarization index.
- **flush\_vacc** (*bool*) – If True, throw away the first accumulation after setting the input selection registers. This is good practice the first time a new polarization pair is read.

**Returns** Complex-valued cross-correlation spectra of *pol1* and *pol2* with accumulation length divided out.

**Return type** `numpy.array`

**get\_status** ()

Get status and error flag dictionaries.

Status keys:

- **acc\_len** : Currently loaded accumulation length in number of spectra.

**Returns** (*status\_dict, flags\_dict*) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize the block, setting (or reading) the accumulation length.

**Parameters** **read\_only** (*bool*) – If False, set the accumulation length to the value provided when this block was instantiated. If True, use whatever accumulation length is currently loaded.

**plot\_corr** (*pol1, pol2, show=False*)

Plot a correlation spectra.

### Parameters

- **pol1** (*int*) – First (unconjugated) polarization index.
- **pol2** (*int*) – Second (conjugated) polarization index.
- **show** (*bool*) – If True, call matplotlib's *show* after plotting

**Returns** matplotlib.Figure

**set\_acc\_len** (*acc\_len*)

Set the number of spectra to accumulate.

**Parameters** **acc\_len** (*int*) – Number of spectra to accumulate

### 2.2.11 Post-FFT Test Vector Control

**class** lwa\_f.blocks.eqtvq.EqTvg (*host, name, n\_streams=64, n\_chans=4096, logger=None*)

Instantiate a control interface for a post-equalization test vector generator block.

**Parameters**

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_streams** (*int*) – Number of independent streams which may be delayed
- **n\_chans** (*int*) – Number of frequency channels.

**get\_status** ()

Get status and error flag dictionaries.

Status keys:

- **tvq\_enabled**: Currently state of test vector generator. True if the generator is enabled, else False.

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize the block.

**Parameters** **read\_only** (*bool*) – If True, do nothing. If False, load frequency-ramp test vectors, but disable the test vector generator.

**read\_stream\_tvq** (*stream*)

Read the test vector loaded to an ADC stream.

**Parameters** **stream** (*int*) – Index of stream from which test vectors should be read.

**Returns** Test vector array, as loaded to the FPGA in 8-bit unsigned integer representation.

**Return type** numpy.ndarray

**tvq\_disable** ()

Disable the test vector generator

**tvq\_enable** ()

Enable the test vector generator.

**tvq\_is\_enabled()**

Query the current test vector generator state.

**Returns** True if the test vector generator is enabled, else False.

**Return type** bool

**write\_const\_per\_stream()**

Write a constant to all the channels of a stream, with stream *i* taking the value *i*.

**write\_freq\_ramp()**

Write a frequency ramp to the test vector that is repeated for all ADC inputs. Data are wrapped to fit into 8 bits. I.e., the test vector value for channel 257 takes the value 1.

**write\_stream\_tvq(stream, test\_vector)**

Write a test vector pattern to a single signal stream.

**Parameters**

- **stream** (*int*) – Index of stream to which test vectors should be loaded.
- **test\_vector** (*list or numpy.ndarray*) – *self.n\_chans*-element test vector. Values should be representable in 8-bit unsigned integer format. Data are loaded such that the most-significant 4 bits of the test\_vectors are interpreted as the 2's complement 4-bit real sample data. The least-significant 4 bits of the test vectors are interpreted as the 2's complement 4-bit imaginary sample data.

## 2.2.12 Equalization Control

**class** lwa\_f.blocks.eq.**Eq**(*host, name, n\_streams=64, n\_coeffs=512, logger=None*)

Instantiate a control interface for an Equalization block.

**Parameters**

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_streams** (*int*) – Number of independent streams which may be delayed
- **n\_coeffs** (*int*) – Number of coefficients per input stream. Coefficients are shared among neighbouring frequency channels.

**clip\_count()**

Get the total number of times any samples have clipped, since last sync.

**Returns** Clip count.

**Return type** int

**get\_coeffs(stream)**

Get the coefficients currently loaded. Reads the actual coefficients from the board.

**Parameters** **stream** (*int*) – ADC stream index to query.

**Returns** (coeffs, binary\_point). *coeffs* is an array of *self.n\_coeffs* integer coefficients currently being applied. *binary\_point* is the position of the binary point by which these integers are scaled on the FPGA.

**Return type** (numpy.ndarray, int)



**get\_status()**

Get status and error flag dictionaries.

Status keys:

- **clip\_count**: Number of clip events in the last sync period.
- **width**: Bit width of coefficients
- **binary\_point**: Binary point position of coefficients
- **coefficients<n>**: The currently loaded, integer-valued coefficients for ADC stream *n*.

**Returns** (*status\_dict*, *flags\_dict*) tuple. *status\_dict* is a dictionary of status key-value pairs. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

**initialize** (*read\_only=False*)

Initialize block.

**Parameters** **read\_only** (*bool*) – If False, set all coefficients to some nominally sane value. Currently, this is 100.0. If True, do nothing.

**set\_coeffs** (*stream*, *coeffs*)

Set the coefficients for a data stream. Clipping and saturation will be applied before loading.

**Parameters**

- **stream** (*int*) – ADC stream index to which coefficients should be applied.
- **coeffs** (*list* or *numpy.ndarray*) – Array of coefficients to load. This should be of length `self.n_coeffs`, else an `AssertionError` will be raised.

## 2.2.13 Channel Selection Control

**class** `lwa_f.blocks.chanreorder.ChanReorder` (*host*, *name*, *n\_chans=1024*, *logger=None*)

Instantiate a control interface for a Channel Reorder block.

**Parameters**

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_chans** (*int*) – Number of channels in the system.

**initialize** (*read\_only=False*)

Initialize the block.

**Parameters** **read\_only** (*bool*) – If True, this method is a no-op. If False, initialize the block with the identity map. I.e., map channel *n* to channel *n*.

**n\_parallel\_chans** = 8

Number of channels per reorder word

**read\_reorder** (*raw=False*)

Read the currently loaded reorder map.

**Parameters** **raw** (*bool*) – If True, return the map as loaded onto the FPGA. If False, return the resulting channel map – i.e., the channel ordering being output by this F-engine.

**Returns** The reorder map currently loaded.

**Return type** *list*

**set\_channel\_order** (*order*)

Re-order channels so that they are sent with the order in the specified map.

There are various requirements of the map which must be met.

- Every integer multiple of *self.n\_parallel\_chans* of the map must start on an integer multiple of *n\_parallel\_chans*. Eg., for *n\_parallel\_chans* = 8 *order*[0] = 16 is acceptable. *order*[0] = 4 is not.
- Blocks of *n\_parallel\_chans* must be consecutive. Eg., if *n\_parallel\_chans*=8, *order*[16:24] = [0,1,2,3,4,5,6,7] is acceptable. *order*[16:24] = [0,1,2,3,8,9,10,11] is not.
- The provided map must be *self.n\_chans* elements long.

**Parameters** **order** (*list of int*) – The order to which data should be mapped. I.e., if *order*[0] = 16, then the first channel out of the F-engine will be channel 16. The order map should meet the above criteria. A *ValueError* exception will be raised if they are not.

## 2.2.14 Packetization Control

**class** `lwa_f.blocks.packetizer.Packetizer` (*host, name, n\_chans=4096, n\_pols=64, sample\_rate\_mhz=200.0, logger=None*)

The packetizer block allows dynamic definition of packet sizes and contents. In firmware, it is a simple block which allows insertion of header entries and EOFs at any point in the incoming data stream. It is up to the user to configure this block such that it behaves in a reasonable manner – i.e.

- Output data rate does not overflow the downstream Ethernet core
- Packets have a reasonable size
- EOFs and headers are correctly placed.

### Parameters

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.
- **n\_chans** (*int*) – Number of frequency channels in the correlation output.
- **n\_pols** (*int*) – Number of independent analog streams in the system
- **sample\_rate\_mhz** (*float*) – ADC sample rate in MHz. Used for data rate checks.

**get\_packet\_info** (*n\_pkt\_chans, occupation=0.95, chan\_block\_size=8*)

Get the packet boundaries for packets containing a given number of frequency channels.

### Parameters

- **n\_pkt\_chans** (*int*) – The number of channels per packet.
- **occupation** (*float*) – The maximum allowed throughput capacity of the underlying link. The calculation does not include application or protocol overhead, so must necessarily be < 1.

- **chan\_block\_size** (*int*) – The granularity with which we can start packets. I.e., packets must start on an  $n \times \text{chan\_block}$  boundary.

#### Returns

packet\_starts, packet\_payloads, channel\_indices

**packet\_starts** [list of ints] The word indexes where packets start – i.e., where headers should be written. For example, a value [0, 1024, 2048, ...] indicates that headers should be written into underlying brams at addresses 0, 1024, etc.

**packet\_payloads** [list of range()] The range of indices where this packet's payload falls. Eg: [range(1,257), range(1025,1281), range(2049,2305), ... etc] These indices should be marked valid, and the last given an EOF.

**channel\_indices** [list of range()] The range of channel indices this packet will send. Eg: [range(1,129), range(1025,1153), range(2049,2177), ... etc] Channels to be sent should be re-indexed so that they fall into these ranges.

**write\_config** (*packet\_starts, packet\_payloads, channel\_indices, ant\_indices, dest\_ips, dest\_ports, print\_config=False*)

Write the packetizer configuration BRAMs with appropriate entries.

#### Parameters

- **packet\_starts** (*list of int*) – Word-indices which are the first entry of a packet and should be populated with headers (see *get\_packet\_info()*)
- **packet\_payloads** (*list of range()s*) – Word-indices which are data payloads, and should be mared as valid (see *get\_packet\_info()*)
- **channel\_indices** (*list of ints*) – Header entries for the channel field of each packet to be sent
- **ant\_indices** (*list of ints*) – Header entries for the antenna field of each packet to be sent
- **dest\_ips** – list of str IP addresses for each packet to be sent.
- **dest\_ports** (*list of int*) – UDP destination ports for each packet to be sent.
- **print** (*bool*) – If True, print config for debugging

All parameters should have identical lengths.

## 2.2.15 Ethernet Output Control

**class** `lwa_f.blocks.eth.Eth` (*host, name, logger=None*)

Instantiate a control interface for a 40 GbE block.

#### Parameters

- **host** (*casperfpga.CasperFpga*) – CasperFpga interface for host.
- **name** (*str*) – Name of block in Simulink hierarchy.
- **logger** (*logging.Logger*) – Logger instance to which log messages should be emitted.

**add\_arp\_entry** (*ip, mac*)

Set a single arp entry.

#### Parameters

- **ip** (*int*) – The last octet of the IP address matching the given MAC.
- **mac** (*int*) – The MAC address to be loaded to the ARP cache.

**disable\_tx** ()

Disable Ethernet transmission.

**enable\_tx** ()

Enable Ethernet transmission.

**get\_status** ()

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. *flags\_dict* is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

**initialize** (*read\_only=False*)

Individual blocks should override this method to configure themselves appropriately

**Parameters** **read\_only** (*bool*) – If False, initialize blocks in a way that might change the configuration of running hardware. If True, read runtime info from blocks, but don't change anything.

**reset** ()

Disable, then reset the 40 GbE core. It must be enabled with `enable_tx` before traffic will be transmitted.

**set\_arp\_table** (*macs*)

Set the ARP table with a list of MAC addresses.

**Parameters** **macs** (*list of int*) – MAC addresses to be loaded into the ARP table. These should be the form of a list of integers, such that the *n*<sup>th</sup> list entry contains the MAC address of the device with IP XXX.XXX.XXX.*n*.

**status\_reset** ()

Reset all status counters.

## 2.3 etcd Interface

The `etcd` F-Engine interface provides a mechanism to control multiple SNAP2 boards running F-Engine firmware via the passing of messages through an `etcd` key-value store.

In order to use the `etcd` control interface, a daemon `Snap2FEngineEtcdClient` instance is required to be running on a server with network access to the SNAP2 hardware being controlled.

### 2.3.1 Key Organization

For an F-Engine running on a SNAP2 `hostname`, there are three relevant `etcd` key paths.

## Command

The command key is:

```
/cmd/snap/<hostname>/command
```

Writing messages to this key results in the execution of `Snap2Engine` command methods.

## Response

Each command written to the command key will elicit a response published to the key:

```
/resp/snap/<hostname>/response
```

The response message will indicate the success or failure of the command, and may contain a command-dependent data payload. For example, a spectra, or snapshot of ADC samples.

## Monitor

In addition to the Command/Response control protocol, general telemetry relating to pipeline element `blockname` can be read from the keys beneath the path:

```
/mon/snap/<hostname>/<blockname>
```

Such keys are intended to be continuously updated on a ~1 second time cadence, and contain low data-volume status information. For example, FPGA temperature, ADC RMS, number of transmitted Ethernet packets, and similar.

## 2.3.2 Command/Response Protocol

The Command/Response protocol is designed to be a simple interface to the underlying `Snap2Engine` control class. It will naturally extend as the control class functionality is expanded.

A simple example of a control client is implemented in the `Snap2EngineEtcdControl` class, which is used for internal testing.

## Command Format

Commands sent to the command key are JSON-encoded dictionaries, and should have the following fields:

Field	Type	Description
<code>sequence_id</code>	integer	A unique integer associated with this command, used to identify the command's response
<code>timestamp</code>	float	The UNIX time when this command was issued
<code>command</code>	string	Command Name
<code>block</code>	string	Firmware block name to which command applies
<code>kwargs</code>	dictionary	Dictionary of arguments required by the <code>block.command</code> method

Allowed values for `block` are any of the keys in the `Snap2Engine` `blocks` attribute. I.e.:

```
from lwa_f import snap2_fengine
f = snap2_fengine.Snap2Fengine('snap2-rev2-11')
for block in sorted(f.blocks.keys()): print(block)
adc
autocorr
corr
delay
eq
eq_tvg
eth
input
noise
packetizer
pfb
reorder
sync
```

Allowed values for ``command`` are any of the methods which can be called against `Snap2Fengine.blocks[block]`. For example, for the `delay` block, allowed commands are:

- `get_max_delay`
- `set_delay`
- `get_delay`
- `initialize`
- `get_status`

All blocks are instances of the generic `Block` class, and thus it is also possible to call parent class methods such as `read_uint` and `write_uint`. These directly manipulate FPGA registers, and should be used with caution.

The ``kwargs`` field should contain any arguments required by the command method being called. For example, the `Fengine delay` block's `set_delay` method requires a `stream` argument (to select which of the 64 SNAP2 data streams is being manipulated) and a `delay` argument (to set the delay for this stream).

As such, in order to set the delay of data stream 5 to 100 adc samples, a command should be issued with:

Field	Value
block	"delay"
command	"set_delay"
kwargs	{"stream": 5, "delay": 100}

An example of a valid command JSON string, issued with the above parameters at UNIX time 1618060712.60 and with `sequence_id=1` is:

```
'{"block": "delay", "timestamp": 1618060712.6, "kwargs": {"delay": 100, "stream": 5}, "command": "set_delay", "sequence_id": 1}'
```

Consult the `Snap2Fengine` API details for a list of commands and their arguments.

## Response Format

Every command sent elicits the writing of JSON-encoded dictionary to the response key. This dictionary has the following fields:

Field	Type	Description
sequence_id	integer	An integer matching the <code>sequence_id</code> field of the command string to which this is a response
timestamp	float	The UNIX time when this response was issued
status	string	The string “normal” if the corresponding command was processed without error, or “error” if it was not.
response	command dependent	The response of the command method, as determined by the command API. If a method would usually return a numpy array, when using the <code>etcd</code> interface the response will be a list. In the event that the status field is “error”, The response field will contain an error message string

Not all `Snap2FEngine` methods return values, in which case the response field is `null`. The previous command example (setting a delay) results in the underlying API call `Snap2FEngine.blocks['delay'].set_delay(5, 100)` which returns `None`. The response to the example command (assuming processing the command took 0.2 milliseconds) is thus:

Field	Value
sequence_id	1
timestamp	1618060712.8
status	"normal"
response	null

or, in JSON-encoded form:

```
'{"sequence_id": 1, "timestamp": 1618060712.8, "status": "normal",
"response": null}'
```

If the response status field is “error”, common response error messages, and their meanings are:

“JSON decode error”	Command string could not be JSON-decoded.
“Sequence ID not integer”	Sequence ID was not provided in the command string or decoded to a non-integer value.
“Bad command format”	Received command did not comply with formatting specifications. E.g. was missing a required field such as <code>block</code> or <code>command</code> .
“Command invalid”	Received command doesn’t exist in the <code>Snap2FEngine</code> API, or is prohibited for <code>etcd</code> access.
“Wrong block”	<code>block</code> field of the command decoded to a block which doesn’t exist.
“Command arguments invalid”	<code>kwargs</code> key contained missing, or unexpected keys.
“Command failed”	The underlying <code>Snap2FEngine</code> API call raised an exception.

In the event that a command fails, more information is available in the `Snap2FEngineEtcdClient` daemon logs.

## Monitoring Interface

autocorr/acc_len	int	Accumulation length, in spectra, of the internal autocorrelation module.
corr/acc_len	int	Accumulation length, in spectra, of the internal correlation module.
delay/n/delay	int	Delay of each of the <i>n</i> data streams.
delay/maxdelay	int	The maximum delay supported by the firmware.
eq/binary_point	int	The position of the EQ coefficient binary point
eq/width	int	The bit width of the EQ coefficients
eq/clip_count	int	The number of clips when requantizing spectra to 4-bit. This counter resets every [TODO: w
eq/n/coefficients	list (int)	The currently loaded coefficients, in integer form (i.e., interpreted with all bits above the bin
eq_tvg/tvg_enabled	bool	True if the post-FFT test vector generator is enabled. False otherwise.
eth/tx_ctr	int	Running count of number of packets transmitted.
eth/tx_err	int	Running count of number of packet errors detected.
eth/tx_full	int	Running count of number of transmission buffer overflow events.
eth/tx_vld	int	Running count of number of 256-bit words transmitted.
feng/flash_firmware	string	The current .fpg bitstream file stored in flash memory
feng/flash_firmware_md5	int	The MD5 checksum of the .fpg bitstream stored in flash
feng/host	string	The hostname of the SNAP2 board
feng/programmed	bool	True if the board appears to be running DSP firmware. False otherwise.
feng/fw_version	string	The version string of the currently running firmware, presented as <code>major_v ersion.min</code>
feng/fw_build_time	int	The time, in seconds since 00:00:00 on 1 January 1970, that the currently running firmware v
feng/serial	string	A notional “serial number” of this hardware. Not yet implemented.
feng/sw_version	string	The software version of the <code>lwa_f</code> python library currently in use
feng/sys_mon	string	“reporting” if the current firmware has a working system monitor module. “not reporting” if
feng/temp	float	FPGA junction temperature, in degrees C, reported by system monitor (if available)
feng/vccaux	float	Voltage of the VCCAUX FPGA power rail reported by system monitor (if available)
feng/vccbram	float	Voltage of the VCCBRAM FPGA power rail reported by system monitor (if available)
feng/vccint	float	Voltage of the VCCINT FPGA power rail reported by system monitor (if available)
input/n/mean	float	Mean of ADC sample values for input ADC <i>n</i> .
input/n/rms	float	RMS of ADC sample values for input ADC <i>n</i> .
input/n/power	float	Mean of squares of ADC sample values for input ADC <i>n</i> .
input/n/switch_position	string	Switch position for input data stream <i>n</i> . <code>noise</code> for internal noise generators, <code>adc</code> for analog
noise/noise_core00_seed	int	Seed value for internal noise generator 0.
noise/noise_core01_seed	int	Seed value for internal noise generator 1.
noise/noise_core02_seed	int	Seed value for internal noise generator 2.
noise/n/output_assignment	int	Noise source (0 - 5) currently assigned to data stream <i>n</i> .
pfb/fft_shift	int	Currently loaded FFT shift schedule.
pfb/overflow_count	int	Running count of FFT overflow events.
sync/ext_count	int	Running count of number of external sync pulses received since FPGA was programmed.
sync/int_count	int	Running count of number of internal sync pulses received since FPGA was programmed.
sync/period_fpga_clks	int	Detected period of external sync pulses in units of FPGA clock cycles.
sync/uptime_secs	int	Number of seconds since FPGA was last programmed



## F-ENGINE REGISTER DEFINITIONS

F-Engine firmware is designed to be manipulated using the provided `Snap2FEngine` class, or its higher level `etcd`-based control interface.

However, individual F-engine registers and their purposes are described below.

### 3.1 Register Descriptions

Register Name	Size (Bytes)	Permission	Description
<b>ADC Registers</b>			
<code>ads5296_controller_&lt;i&gt;j&lt;/i&gt;</code>	4096	r/w	ADS5296 board control register for the <i>j</i> th ADC card in FMC <i>i</i> . Should be manipulated using the <code>ADS5296</code> class of the <code>casperfpga</code> python library.
<code>ads5296_spi_controller_&lt;i&gt;i&lt;/i&gt;</code>	4	r/w	ADS5296 SPI controller register for ADC cards on FMC slot <i>i</i> . Should be manipulated using the <code>ADS5296</code> class of the <code>casperfpga</code> python library.
<code>ads5296_wram_&lt;i&gt;i&lt;/i&gt;_&lt;j&gt;_&lt;k&gt;</code>	4096	r/w	ADC snapshot RAM for ADC chip <i>k</i> on board <i>j</i> of FMC port <i>i</i> . Should be manipulated using the <code>ADS5296</code> class of the <code>casperfpga</code> python library.
<code>adc_rst</code>	4	r/w	Set to 1 to assert the ADC reset. This flushes the ADC output FIFOs. Data will not begin flowing again until the ADC <code>sync</code> input transitions from 0 to 1.
<code>adc_snapshot_trigger</code>	4	r/w	When this register transitions from 0 to 1, all ADC channels will simultaneously capture a burst of ADC samples.
<code>adc_sync</code>	4	r/w	Write 1 to this register to assert the ADC's <code>sync</code> input. This input is edge sensitive.
<b>Auto-Correlator Registers</b>			
<code>autocorr_acq_cnt</code>	4	r	32-bit wrapping accumulation counter, which increments each time a new accumulation is recorded to RAM. There is no buffer locking when correlation data are read, so this counter can be used to ensure that data have not changed during a read.
<code>autocorr_acq_len</code>	4	r/w	Accumulation length, in spectra.
<code>autocorr_combine_&lt;n&gt;_bram</code>	262144	r/w	For memory name suffix <code>&lt;n&gt;_bram</code> , stores the autocorrelation powers for frequency channels <i>n</i> of 16 consecutive F-engine inputs. Data are stored in <code>[input_number, freq_channel]</code> order.

continues on next page

Table 3.1 – continued from previous page

Register Name	Size (Bytes)	Permission	Description
autocorr_corr0_acc4_dout1	262144	r/wbram	For memory name suffix <n>_bram, stores the autocorrelation powers for frequency channels $8n$ of 16 consecutive F-engine inputs. Data are stored in [input_number, freq_channel] order.
autocorr_corr0_acc4_dout2	262144	r/wbram	For memory name suffix <n>_bram, stores the autocorrelation powers for frequency channels $8n$ of 16 consecutive F-engine inputs. Data are stored in [input_number, freq_channel] order.
autocorr_corr0_acc4_dout3	262144	r/wbram	For memory name suffix <n>_bram, stores the autocorrelation powers for frequency channels $8n$ of 16 consecutive F-engine inputs. Data are stored in [input_number, freq_channel] order.
autocorr_corr0_acc4_dout4	262144	r/wbram	For memory name suffix <n>_bram, stores the autocorrelation powers for frequency channels $8n$ of 16 consecutive F-engine inputs. Data are stored in [input_number, freq_channel] order.
autocorr_corr0_acc4_dout5	262144	r/wbram	For memory name suffix <n>_bram, stores the autocorrelation powers for frequency channels $8n$ of 16 consecutive F-engine inputs. Data are stored in [input_number, freq_channel] order.
autocorr_corr0_acc4_dout6	262144	r/wbram	For memory name suffix <n>_bram, stores the autocorrelation powers for frequency channels $8n$ of 16 consecutive F-engine inputs. Data are stored in [input_number, freq_channel] order.
autocorr_corr0_acc4_dout7	262144	r/wbram	For memory name suffix <n>_bram, stores the autocorrelation powers for frequency channels $8n$ of 16 consecutive F-engine inputs. Data are stored in [input_number, freq_channel] order.
autocorr_max_sel	4	r/w	Input selection controller. Set bits [1:0] to $n$ to compute the autocorrelations of F-engine inputs $16n \dots 16(n+1) - 1$ .
<b>Channel Re-order Registers</b>			
chan_reorder_acc4amic_remap1	16384	r/wbram	Determines the remapping of input samples to output samples. I.e., if the first entry is 5, then the first sample into the reorder will come out 5th
<b>Correlation Registers</b>			
corr_0_acc4_cnt	4	r	32-bit wrapping accumulation counter, which increments each time a new accumulation is recorded to RAM. There is no buffer locking when correlation data are read, so this counter can be used to ensure that data have not changed during a read.
corr_0_acc4_en	4	r/w	Accumulation length, in FPGA clock cycles. To specify an accumulation length as a number of spectra this register should be written with <code>number_of_spectra x frequency_channels_per_spectra</code> . Here the number of frequency channels per spectra is the number <i>output</i> by the correlation subsystem. Glitches may occur (resulting in the no new accumulations for a few seconds) if the value in this register is reduced without re-applying a sync to the correlation module.
corr_0_dout2768	82768	r/w	Correlation data buffer. Word [2n] is the real part of the correlation of frequency channel $n$ (after any channel averaging). Word [2n+1] is the imaginary part of this correlation.
corr_0_input_sel	4	r/w	Input selector control register. Bits [5:0] select the unconjugated correlation input. Bits [13:8] select the conjugated correlation input.

continues on next page

Table 3.1 – continued from previous page

Register Name	Size (Bytes)	Permission	Description
<b>Delay Registers</b>			
delay_<n>	4	r/w	The delay applied to stream <i>n</i> . Any value entered in this 32-bit register will be interpreted modulo the maximum supported delay.
delay_max	4	r	Interpretted as a uint32 value, contains the maximum allowed delay, in ADC samples, which may be applied to a data stream.
<b>Equalization Registers</b>			
eq_core<n>	4	r	A count of the number of times a sample has been clipped, for any of F-engine inputs $16n \dots 16(n+1) - 1$ . This counter is reset only by a global system reset.
eq_core<n>	131072	r/w	This memory holds coefficients for F-engine streams $16n \dots 16(n+1) - 1$ . Coefficients are stored as a $[16, \text{n\_fft\_channels} / 8]$ array, where the first axis (over input number) varies <i>slowest</i> . Coefficients are shared over 8 consecutive frequency channels, with coefficient <i>m</i> being applied to frequency channel $m \dots 8(m+1) - 1$ . Coefficients are interpreted with 5 bits below the binary point.
<b>40GbE Registers</b>			
eth_ctrl	4	r/w	40GbE control register. Bit 0 is an active high reset of the 40GbE interface core. Bit 1 is an active high transmission enable for the core, which takes effect either after the next packet is sent, or when the <i>force</i> flag is asserted. Bit 18 is an active high reset for statistics provided by the Ethernet core. Bit 19 is an active high <i>force</i> signal, which causes the current transmission enable flag to immediately take effect.
eth_forty_gbe_txctr	4	r	Counter which increments each time a valid end-of-frame is seen on a packet to be transmitted
eth_forty_gbe_txfullctr	4	r	Counter which increments every time the transmission buffer is full
eth_forty_gbe_txofctr	4	r	Counter which increments on every transmission overflow event
eth_forty_gbe_txvldctr	4	r	Counter which increments with every valid word of data input to the core
<b>Input Control Registers</b>			
input_bit_stats	131072	r/w	BRAM storing histogram data. Word <i>n</i> in the bottom half of the RAM stores the number of occurrences of of ADC sample code <i>n</i> in <i>_even_</i> numbered ADC samples. Word <i>n</i> in the <i>_top_</i> half of the RAM stores the number of occurrences of ADC sample code <i>n</i> in <i>_odd_</i> numbered ADC samples.
input_bit_stats_input_sel	6	r/w	Input selection. The least significant 6 bits should be set to <i>n</i> to compute the histogram for input <i>n</i> .
input_rms_enable	1	r/w	Enable statistics recording. If the least-significant bit is 1, statistics will be recorded to RAM.
input_rms_data	65536	r/w	Multi-channel statistics. For the <i>n</i> th 64-bit word, the least significant 32 bits represent the accumulated ADC power, accumulated over 65536 samples and stored as an unsigned 32-bit integer. The most significant 32 bits represent the sum of 65536 ADC samples stored as a signed 32-bit integer.

continues on next page

Table 3.1 – continued from previous page

Register Name	Size (Bytes)	Permission	Description
input_source4_sel0	4	r/w	Selector control to determine if signal streams carry ADC samples, digital noise samples, or zeros. Streams $n=0..15$ is controlled by register bits $[2n+1:2n]$ . Value 0 selects noise; 1 selects ADC; 2 selects zeros.
input_source4_sel1	4	r/w	Selector control to determine if signal streams carry ADC samples, digital noise samples, or zeros. Streams $n=16..31$ is controlled by register bits $[2(n-16)+1:2(n-16)]$ . Value 0 selects noise; 1 selects ADC; 2 selects zeros.
input_source4_sel2	4	r/w	Selector control to determine if signal streams carry ADC samples, digital noise samples, or zeros. Streams $n=32..47$ is controlled by register bits $[2(n-32)+1:2(n-32)]$ . Value 0 selects noise; 1 selects ADC; 2 selects zeros.
input_source4_sel3	4	r/w	Selector control to determine if signal streams carry ADC samples, digital noise samples, or zeros. Streams $n=48..63$ is controlled by register bits $[2(n-48)+1:2(n-48)]$ . Value 0 selects noise; 1 selects ADC; 2 selects zeros.
<b>Noise Generator Registers</b>			
noise_octal4mux0_sel	4	r/w	The lower 2 bits define the select signal for the noise multiplexor. If this register has value $v$ , then noise generator $v$ is selected.
noise_octal4mux1_sel	4	r/w	The lower 2 bits define the select signal for the noise multiplexor. If this register has value $v$ , then noise generator $v$ is selected.
noise_octal4mux2_sel	4	r/w	The lower 2 bits define the select signal for the noise multiplexor. If this register has value $v$ , then noise generator $v$ is selected.
noise_octal4mux3_sel	4	r/w	The lower 2 bits define the select signal for the noise multiplexor. If this register has value $v$ , then noise generator $v$ is selected.
noise_octal4mux4_sel	4	r/w	The lower 2 bits define the select signal for the noise multiplexor. If this register has value $v$ , then noise generator $v$ is selected.
noise_octal4mux5_sel	4	r/w	The lower 2 bits define the select signal for the noise multiplexor. If this register has value $v$ , then noise generator $v$ is selected.
noise_octal4mux6_sel	4	r/w	The lower 2 bits define the select signal for the noise multiplexor. If this register has value $v$ , then noise generator $v$ is selected.
noise_octal4mux7_sel	4	r/w	The lower 2 bits define the select signal for the noise multiplexor. If this register has value $v$ , then noise generator $v$ is selected.
noise_seeds0	40	r/w	Noise generator seed values. If the 32-bit value in this register is $v$ , the seed for the first noise generator is (using Verilog syntax) $\{8'h5c, v[7:0], v[0:7], 8'ha3\}$ . The seed for the second noise generator is $\{8'h5c, v[15:8], v[8:15], 8'ha3\}$ . The seed for the third noise generator is $\{8'h5c, v[23:16], v[16:23], 8'ha3\}$ . The seed for the fourth noise generator is $\{8'h5c, v[31:24], v[24:31], 8'ha3\}$
<b>Packetizer Registers</b>			
packetizer_262	144	r/w	Antenna header entry map. Word $n$ contains the header antenna ID field for sample $n$ in a transmission period. This field is only relevant for samples accompanied by valid and header flags.

continues on next page

Table 3.1 – continued from previous page

Register Name	Size (Bytes)	Permissions	Description
packetizer_0_chns	16	r/w	Channel ID header entry map. Bits [23:0] of word $n$ contain the header channel ID field for sample $n$ in a transmission period. This header field should hold the index of the first channel in a packet. Bits [31:24] contain the header channel block index field for this sample. These field is only relevant for samples accompanied by <code>valid</code> and <code>header</code> flags.
packetizer_0_flags	16	r/w	Packet flags. For word $n$ , bit 0 is an active high flag which indicates that sample $n$ in a transmission period is a packet header. Bit 8 is an active high flag which indicates that this word is valid and should be transmitted. Bit 16 is an active high flag indicating that this word is the last in a packet.
packetizer_0_ip	16	r/w	IP Destination address map. Word $n$ contains the IP address to which sample $n$ in a transmission period should be sent. Only entries accompanied by <code>valid</code> and <code>end of frame</code> flags result in a packet's destination being set from this register.
packetizer_4_chans	4	r/w	32-bit <code>n_chans</code> header field for F-engine output data packets, indicating the number of frequency channels per packet.
packetizer_4_pols	4	r/w	32-bit <code>n_pols</code> header field for F-engine output data packets, indicating the number of antenna-polarizations present in a packet.
packetizer_0_udp	16	r/w	UDP Destination port map. For word $n$ , bits [15:0] contain the UDP port to which sample $n$ in a transmission period should be sent. Only samples accompanied by <code>valid</code> and <code>end of frame</code> flags result in a packet's destination being set from this register.
<b>PFB Registers</b>			
pfb_ctrl	4	r/w	PFB control register. Bit 18 is an active-high reset for overflow statistics counters. Bits 15:0 hold the FFT shift schedule for the PFB processing pipeline, with bit $n$ an active high shift signal for the $n$ th FFT stage.
pfb_pfb16x4<n>_status	16	r	A 32-bit counter which, for register name suffix <code>&lt;n&gt;_status</code> increments every time an FFT overflow event is detected in any of FFT channels $16n \dots 16(n+1)-1$ . Resets only when commanded via the PFB control register, and will wrap once the maximum value is reached.
<b>Post-EQ Test Vector Generator Registers</b>			
post_eq_tvgs_4<n>_tv	524288	r/w	This memory holds 4+4 bit complex test vector streams for F-engine streams $16n \dots 16(n+1)-1$ . Test vectors are stored as a [16, <code>n_fft_channels</code> ] array, where the first axis (over input number) varies <i>slowest</i> , and vectors are stored in order of increasing FFT channel. An 8-bit word in location [ $m$ , $c$ ] is interpreted as a 4+4 bit complex value for channel $c$ of F-engine stream $16n + m$ . The most significant 4 bits are interpreted as the real part of the complex value.
post_eq_tvgs_4_tv_en	4	r/w	Test vector multiplexor control. If the least significant bit is 1, ADC data will be replaced with software-controllable test vectors.

continues on next page

Table 3.1 – continued from previous page

Register Name	Size (Bytes)	Permission	Description
<b>Synchronization Registers</b>			
sync_ctrl	4	r/w	Timing control register. Bit 0: active high enable allowing telescope time counter to be loaded from telescope time load registers on next synchronization pulse. Bit 1: When transitioned from 0 to 1, forces telescope time counter to be loaded from telescope time load registers immediately. Bit 2: active high telescope time counter reset. Bit 3: active high reset for error counters. Bit 4: active high arm signal, which causes a global system reset, released on the next synchronization pulse; a system sync on the next synchronization pulse. Bit 5: When transitioned from 0 to 1, emulates the arrival of an external sync pulse. Bit 6: When transitioned from 0 to 1, arms noise generator seed loaders.
sync_ext_sync_count	4	r	Number of external synchronization pulses received.
sync_ext_sync_period	4	r	Measured number of FPGA clock ticks between previous two external synchronization pulses.
sync_ext_sync_tt_lsb	4	r	Least significant 32 bits of the telescope time counter, at the point of the last external synchronization pulse.
sync_ext_sync_tt_msb	4	r	Most significant 32 bits of the telescope time counter, at the point of the last external synchronization pulse.
sync_int_sync_count	4	r	Number of synchronization pulses emitted via GPIO.
sync_latency	4	r	Measured latency, in FPGA clock ticks, between transmitting a synchronization pulse and receiving it from the timing distribution system.
sync_sync_div_bits	4	r	Holds the log2 value of the sync period – i.e. the rate at which sync pulses are emitted from the board via GPIO – in FPGA clock ticks.
sync_tt_load_lsb	4	r/w	Telescope time load register. Least significant 32 bits to load to the telescope time counter.
sync_tt_load_msb	4	r/w	Telescope time load register. Most significant 32 bits to load to the telescope time counter.
sync_tt_lsb	4	r	Least significant 32 bits of the telescope time counter.
sync_tt_msb	4	r	Most significant 32 bits of the telescope time counter.
sync_uptime	4	r	Board uptime, in units of $2^{32}$ FPGA clock ticks.
<b>Version Registers</b>			
version_timestamp	4	r	Unix timestamp, in integer seconds, when firmware was last compiled.
version_version	4	r	Version register. Bits [31:24]: major version. Bits [23:16]: minor version. Bits [15:8]: revision. Bits [7:0]: buxfix.

## INDICES AND TABLES

- `genindex`
- `modindex`
- `search`





## A

Adc (class in lwa\_f.blocks.adc), 10  
 adc (lwa\_f.snap2\_fengine.Snap2Fengine attribute), 6  
 add\_arp\_entry() (lwa\_f.blocks.eth.Eth method), 23  
 arm\_noise() (lwa\_f.blocks.sync.Sync method), 9  
 arm\_sync() (lwa\_f.blocks.sync.Sync method), 9  
 assign\_output() (lwa\_f.blocks.noisegen.NoiseGen method), 14  
 AutoCorr (class in lwa\_f.blocks.autocorr), 16  
 autocorr (lwa\_f.snap2\_fengine.Snap2Fengine attribute), 6

## B

blocks (lwa\_f.snap2\_fengine.Snap2Fengine attribute), 6

## C

calibrate() (lwa\_f.blocks.adc.Adc method), 10  
 ChanReorder (class in lwa\_f.blocks.chanreorder), 21  
 clip\_count() (lwa\_f.blocks.eq.Eq method), 20  
 configure\_output() (lwa\_f.snap2\_fengine.Snap2Fengine method), 6  
 Corr (class in lwa\_f.blocks.corr), 18  
 corr (lwa\_f.snap2\_fengine.Snap2Fengine attribute), 6  
 count\_ext() (lwa\_f.blocks.sync.Sync method), 9  
 count\_int() (lwa\_f.blocks.sync.Sync method), 9

## D

Delay (class in lwa\_f.blocks.delay), 15  
 delay (lwa\_f.snap2\_fengine.Snap2Fengine attribute), 6  
 disable\_tx() (lwa\_f.blocks.eth.Eth method), 24

## E

enable\_tx() (lwa\_f.blocks.eth.Eth method), 24  
 Eq (class in lwa\_f.blocks.eq), 20  
 eq (lwa\_f.snap2\_fengine.Snap2Fengine attribute), 6  
 eq\_tvg (lwa\_f.snap2\_fengine.Snap2Fengine attribute), 6  
 EqTvg (class in lwa\_f.blocks.eqtvg), 19  
 Eth (class in lwa\_f.blocks.eth), 23  
 eth (lwa\_f.snap2\_fengine.Snap2Fengine attribute), 6

## F

Fpga (class in lwa\_f.blocks.fpga), 7  
 fpga (lwa\_f.snap2\_fengine.Snap2Fengine attribute), 6

## G

get\_acc\_len() (lwa\_f.blocks.autocorr.AutoCorr method), 17  
 get\_acc\_len() (lwa\_f.blocks.corr.Corr method), 18  
 get\_all\_histograms() (lwa\_f.blocks.input.Input method), 12  
 get\_bit\_stats() (lwa\_f.blocks.input.Input method), 12  
 get\_build\_time() (lwa\_f.blocks.fpga.Fpga method), 7  
 get\_coeffs() (lwa\_f.blocks.eq.Eq method), 20  
 get\_delay() (lwa\_f.blocks.delay.Delay method), 15  
 get\_error\_count() (lwa\_f.blocks.sync.Sync method), 9  
 get\_firmware\_version() (lwa\_f.blocks.fpga.Fpga method), 7  
 get\_histogram() (lwa\_f.blocks.input.Input method), 12  
 get\_latency() (lwa\_f.blocks.sync.Sync method), 9  
 get\_max\_delay() (lwa\_f.blocks.delay.Delay method), 15  
 get\_new\_corr() (lwa\_f.blocks.corr.Corr method), 18  
 get\_new\_spectra() (lwa\_f.blocks.autocorr.AutoCorr method), 17  
 get\_output\_assignment() (lwa\_f.blocks.noisegen.NoiseGen method), 14  
 get\_packet\_info() (lwa\_f.blocks.packetizer.Packetizer method), 22  
 get\_seed() (lwa\_f.blocks.noisegen.NoiseGen method), 14  
 get\_snapshot() (lwa\_f.blocks.adc.Adc method), 10  
 get\_snapshot\_interleaved() (lwa\_f.blocks.adc.Adc method), 10  
 get\_status() (lwa\_f.blocks.autocorr.AutoCorr method), 17  
 get\_status() (lwa\_f.blocks.corr.Corr method), 18

`get_status()` (*lwa\_f.blocks.delay.Delay method*), 15  
`get_status()` (*lwa\_f.blocks.eq.Eq method*), 20  
`get_status()` (*lwa\_f.blocks.eqtv.EqTvg method*), 19  
`get_status()` (*lwa\_f.blocks.eth.Eth method*), 24  
`get_status()` (*lwa\_f.blocks.fpga.Fpga method*), 8  
`get_status()` (*lwa\_f.blocks.input.Input method*), 12  
`get_status()` (*lwa\_f.blocks.noisegen.NoiseGen method*), 14  
`get_status()` (*lwa\_f.blocks.pfb.Pfb method*), 16  
`get_status()` (*lwa\_f.blocks.sync.Sync method*), 9  
`get_status_all()` (*lwa\_f.snap2\_fengine.Snap2Fengine method*), 7  
`get_switch_positions()` (*lwa\_f.blocks.input.Input method*), 13

## H

`hostname` (*lwa\_f.snap2\_fengine.Snap2Fengine attribute*), 7

## I

`initialize()` (*lwa\_f.blocks.adc.Adc method*), 11  
`initialize()` (*lwa\_f.blocks.autocorr.AutoCorr method*), 17  
`initialize()` (*lwa\_f.blocks.chanreorder.ChanReorder method*), 21  
`initialize()` (*lwa\_f.blocks.corr.Corr method*), 18  
`initialize()` (*lwa\_f.blocks.delay.Delay method*), 16  
`initialize()` (*lwa\_f.blocks.eq.Eq method*), 21  
`initialize()` (*lwa\_f.blocks.eqtv.EqTvg method*), 19  
`initialize()` (*lwa\_f.blocks.eth.Eth method*), 24  
`initialize()` (*lwa\_f.blocks.input.Input method*), 13  
`initialize()` (*lwa\_f.blocks.noisegen.NoiseGen method*), 15  
`initialize()` (*lwa\_f.blocks.pfb.Pfb method*), 16  
`initialize()` (*lwa\_f.blocks.sync.Sync method*), 9  
`initialize()` (*lwa\_f.snap2\_fengine.Snap2Fengine method*), 7  
`Input` (*class in lwa\_f.blocks.input*), 12  
`input` (*lwa\_f.snap2\_fengine.Snap2Fengine attribute*), 7  
`is_programmed()` (*lwa\_f.blocks.fpga.Fpga method*), 8

## L

`load_telescope_time()` (*lwa\_f.blocks.sync.Sync method*), 9

## M

`MIN_DELAY` (*lwa\_f.blocks.delay.Delay attribute*), 15  
`mmcm_is_locked()` (*lwa\_f.blocks.adc.Adc method*), 11

## N

`n_parallel_chans` (*lwa\_f.blocks.chanreorder.ChanReorder attribute*), 21

`noise` (*lwa\_f.snap2\_fengine.Snap2Fengine attribute*), 7  
`NoiseGen` (*class in lwa\_f.blocks.noisegen*), 14

## P

`Packetizer` (*class in lwa\_f.blocks.packetizer*), 22  
`packetizer` (*lwa\_f.snap2\_fengine.Snap2Fengine attribute*), 7  
`period()` (*lwa\_f.blocks.sync.Sync method*), 9  
`Pfb` (*class in lwa\_f.blocks.pfb*), 16  
`pfb` (*lwa\_f.snap2\_fengine.Snap2Fengine attribute*), 7  
`plot_corr()` (*lwa\_f.blocks.corr.Corr method*), 18  
`plot_histogram()` (*lwa\_f.blocks.input.Input method*), 13  
`plot_spectra()` (*lwa\_f.blocks.autocorr.AutoCorr method*), 17  
`print_histograms()` (*lwa\_f.blocks.input.Input method*), 13  
`print_status_all()` (*lwa\_f.snap2\_fengine.Snap2Fengine method*), 7  
`print_sweep()` (*lwa\_f.blocks.adc.Adc method*), 11

## R

`read_reorder()` (*lwa\_f.blocks.chanreorder.ChanReorder method*), 21  
`read_stream_tvg()` (*lwa\_f.blocks.eqtv.EqTvg method*), 19  
`reorder` (*lwa\_f.snap2\_fengine.Snap2Fengine attribute*), 7  
`reset()` (*lwa\_f.blocks.adc.Adc method*), 11  
`reset()` (*lwa\_f.blocks.eth.Eth method*), 24  
`reset_error_count()` (*lwa\_f.blocks.sync.Sync method*), 9  
`reset_telescope_time()` (*lwa\_f.blocks.sync.Sync method*), 9

## S

`set_acc_len()` (*lwa\_f.blocks.autocorr.AutoCorr method*), 17  
`set_acc_len()` (*lwa\_f.blocks.corr.Corr method*), 19  
`set_arp_table()` (*lwa\_f.blocks.eth.Eth method*), 24  
`set_channel_order()` (*lwa\_f.blocks.chanreorder.ChanReorder method*), 22  
`set_coeffs()` (*lwa\_f.blocks.eq.Eq method*), 21  
`set_delay()` (*lwa\_f.blocks.delay.Delay method*), 16  
`set_delays()` (*lwa\_f.blocks.adc.Adc method*), 11  
`set_seed()` (*lwa\_f.blocks.noisegen.NoiseGen method*), 15  
`Snap2Fengine` (*class in lwa\_f.snap2\_fengine*), 6  
`status_reset()` (*lwa\_f.blocks.eth.Eth method*), 24  
`sw_sync()` (*lwa\_f.blocks.sync.Sync method*), 10  
`sync` (*class in lwa\_f.blocks.sync*), 9  
`sync` (*lwa\_f.snap2\_fengine.Snap2Fengine attribute*), 7

`sync()` (*lwa\_f.blocks.adc.Adc method*), [12](#)

## T

`tvb_disable()` (*lwa\_f.blocks.eqtvb.EqTvg method*),  
[19](#)

`tvb_enable()` (*lwa\_f.blocks.eqtvb.EqTvg method*), [19](#)

`tvb_is_enabled()` (*lwa\_f.blocks.eqtvb.EqTvg method*), [19](#)

## U

`uptime()` (*lwa\_f.blocks.sync.Sync method*), [10](#)

`use_adc()` (*lwa\_f.blocks.input.Input method*), [13](#)

`use_noise()` (*lwa\_f.blocks.input.Input method*), [13](#)

`use_zero()` (*lwa\_f.blocks.input.Input method*), [13](#)

## W

`wait_for_sync()` (*lwa\_f.blocks.sync.Sync method*),  
[10](#)

`write_config()` (*lwa\_f.blocks.packetizer.Packetizer method*), [23](#)

`write_const_per_stream()`  
(*lwa\_f.blocks.eqtvb.EqTvg method*), [20](#)

`write_freq_ramp()` (*lwa\_f.blocks.eqtvb.EqTvg method*), [20](#)

`write_stream_tvb()` (*lwa\_f.blocks.eqtvb.EqTvg method*), [20](#)