# LWA352 SNAP2 F-Engine Documentation

Release 1.0.0

**Jack Hickish** 

# **CONTENTS:**

1	Installation	3		
	1.1       Get the Source Code			
2	Control Interface	5		
	2.1 Overview			
	2.2 SNAP2Fengine Python Interface			
	2.3 etcd Interface	16		
3	3 Indices and tables			
In	lex	23		

Contents:

CONTENTS: 1

2 CONTENTS:

**CHAPTER** 

ONE

## INSTALLATION

The LWA 352 F-Engine pipeline is available at https://github.com/realtimeradio/caltech-lwa. Follow the following instructions to download and install the pipeline.

Specify the build directory by defining the BUILDDIR environment variable, eg:

```
export BUILDDIR=~/src/mkdir -p $BUILDDIR
```

# 1.1 Get the Source Code

Clone the repository and its dependencies with:

```
# Clone the main repository
cd $BUILDDIR
git clone https://github.com/realtimeradio/caltech-lwa
# Clone relevant submodules
cd caltech-lwa
git submodule init
git submodule update
```

# 1.2 Install Prerequisites

# 1.2.1 Firmware Requirements

The LWA-253 F-Engine firmware can be built with the CASPER toolflow, and was designed using the following software stack:

- Ubuntu 18.04.0 LTS (64-bit)
- MATLAB R2019a
- Simulink R2019a
- MATLAB Fixed-Point Designer Toolbox R2019a
- Xilinx Vivado HLx 2019.1.3
- Python 3.6.9

It is *strongly* recommended that the same software versions be used to rebuild the design.

# **CONTROL INTERFACE**

# 2.1 Overview

A Python class Snap2Fengine is provided to encapsulate control of individual blocks in the firmware DSP pipeline. The structure of the software interface aims to mirror the hierarchy of the firmware modules, through the use of multiple Block class instances, each of which encapsulates control of a single module in the firmware pipeline.

In testing, and interactive debugging, the Snap2Fengine class provides an easy way to probe board status for a SNAP2 board on the local network.

In order to integrate with the larger LWA352 control framework, control and monitoring of multiple F-Engines can also be carried out through the passing of JSON-encoded messages through an etcd<sup>1</sup> key-value store. This mechanismi, shown in Fig. 2.1, utilizes the Python class Snap2FengineEtcdClient to translate commands and responses between the etcd format and the underlying Snap2Fengine method calls.




Fig. 2.1: The top-level control architecture.

<sup>&</sup>lt;sup>1</sup> See etcd.io

# 2.2 SNAP2Fengine Python Interface

# 2.2.1 Top-Level Control

```
class lwa_f.snap2_fengine.Snap2Fengine(host, logger=None)
```

**configure\_output** (base\_ant, n\_chans\_per\_packet, chans, ips, ports=None, ants=None)

# 2.2.2 Timing Control

**class** lwa\_f.blocks.delay.**Delay** (*host*, *name*, *n\_streams=64*, *logger=None*) Instantiate a control interface for a Delay block.

#### **Parameters**

- host (casperfpga.CasperFpga) CasperFpga interface for host.
- name (str) Name of block in Simulink hierarchy.
- logger (logging.Logger) Logger instance to which log messages should be emitted.
- n\_streams (int) Number of independent streams which may be delayed

```
MIN_DELAY = 5
```

minimum delay allowed

```
get_delay (stream)
```

Get the current delay for a given input.

Parameters stream (int) - Which ADC input index to query

**Returns** Currently loaded delay, in ADC samples

Return type int

```
get_max_delay()
```

Query the firmware to get the maximum delay it supports.

**Returns** Maximum supported delay, in ADC samples

**Return type** int

```
get_status()
```

Get status and error flag dictionaries.

Status keys:

- delay<n>: Currently loaded delay for ADC input index n.
- max\_delay: The maximum delay supported by the firmware.
- min\_delay: The minimum delay supported by the firmware.

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. flags\_dict is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

```
initialize(read_only=False)
```

Initialize all delays.

**Parameters read\_only** (bool) – If True, do nothing. If False, initialize all delays to the minimum allowed value.

#### set\_delay (stream, delay)

Set the delay for a given input stream.

#### **Parameters**

- **stream** (*int*) ADC stream index to which delay should be applied.
- **delay** (*int*) Number of ADC clock cycles delay to load.

#### 2.2.3 ADC Control

class lwa\_f.blocks.adc.Adc(host, name, logger=None)
Instantiate a control interface for an ADC block.

#### **Parameters**

- host (casperfpga.CasperFpga) CasperFpga interface for host.
- name (str) Name of block in Simulink hierarchy.
- logger (logging.Logger) Logger instance to which log messages should be emitted.

#### calibrate (use\_ramp=False)

Compute and set all ADC data lane input delays to their optimal values. After this call, the ADCs are left in test mode.

**Parameters use\_ramp** (bool) – If True, after calibration, use the ramp test pattern to verify the ADC->FPGA link is functioning correctly. If False, perform this verification with the same constant test value used for the calibration procedure.

**Returns** True if the calibration procedure succeeded. False otherwise.

#### Return type bool

#### get\_snapshot (fmc, signed=False, trigger=True)

Read a snapshot of data from all ADC channels on a single FMC card. Return data without interleaving ADC cores.

#### **Parameters**

- **fmc** (*int*) Which FMC port (0 or 1) to read.
- **signed** (bool) If True, return data interpretted as signed 2's complement integers. If False, return data as unsigned integers.
- **trigger** (bool) If True, trigger a new simultaneous capture of data from all channels. If False, read existing data capture. Grabbing data without a new trigger may be useful if you wish to read channels from a second FMC port which were captured simultaneously with another port.

**Returns** numpy array of captured data with dimensions [ADC\_CHIPS\_PER\_FMC, ADC\_LANES, TIME\_SAMPLES]. Data from ADC lanes representing the same analog input are \_not\_ interleaved. Data from ADC lanes n,n+1 are associated with the same analog input.

Return type numpy.ndarray

#### get\_snapshot\_interleaved(fmc, signed=False, trigger=True)

Read a snapshot of data from all ADC channels on a single FMC card. Return data with ADC cores interleaved.

#### **Parameters**

- fmc (int) Which FMC port (0 or 1) to read.
- **signed** (bool) If True, return data interpretted as signed 2's complement integers. If False, return data as unsigned integers.
- **trigger** (bool) If True, trigger a new simultaneous capture of data from all channels. If False, read existing data capture. Grabbing data without a new trigger may be useful if you wish to read channels from a second FMC port which were captured simultaneously with another port.

**Returns** numpy array of captured data with dimensions [ADC\_CHANNELS\_PER\_FMC, TIME\_SAMPLES].

Return type numpy.ndarray

initialize(read\_only=False, clocksource=1)

Initialize connected ADC boards.

#### **Parameters**

- read\_only (bool) If True, don't do anything which would affect a running system. If False, train ADC->FPGA data links.
- **clocksource** (*int*) Which ADC board (0 or 1) on an FMC card should serve as the source of the clocks. Note that while this parameter is set for boards on all FMC cards, only the FMC card selected as the clock source at Simulink compile-time will be used for clocking.

**Returns** True if initialization was successful. False otherwise.

#### mmcm is locked()

Read the ADC control register to determine if the clock PLLs are locked.

**Returns** True if the ADC clocks are locked. False otherwise.

Return type bool

#### print\_sweep (errs, best\_delays=None, step\_size=4)

Print, using ASCII, the valid data capture eye as a function of delay setting. Delays are printed such that one row represents a sweep of delays for a single ADC data lane. Each column in the row is  $\times$  if data contained errors at this delay, – if no errors were detected at this delay, and  $\mid$ , if this delay is considered the best setting in the sweep range.

#### **Parameters**

- errs (numpy.ndarray) Array of error counts with dimensions [DE-LAY\_TRIALS, ADC\_CHIPS, DATA\_LANES\_PER\_ADC\_CHIP] such as that returned by \_get\_errs\_by\_delay.
- best\_delays (numpy.ndarray) Array of best delays, with shape [ADC\_CHIPS, DATA\_LANES\_PER\_ADC\_CHIP], such as that returned by \_get\_best\_delays. These delays are marked with an ASCII |.
- **step\_size** (*int*) Number of IDELAY tap steps between delay trials.

#### reset()

Toggle the ADC reset input.

#### set delays (adc, delays)

Set IDELAY tap values for all ADC data lanes on an FMC port.

#### **Parameters**

- adc (casperfpga.ads5296.AD5296) ADS5296 object associated with an FMC ADC interface.
- **delays** (numpy.ndarray) Array of delays to load, with shape [ADC\_CHIPS, DATA LANES PER ADC CHIP], such as that returned by get best delays.

#### sync()

Toggle the ADC sync input.

## 2.2.4 Input Control

class lwa\_f.blocks.input.Input (host, name, n\_streams=64, n\_bits=10, logger=None)

#### get\_all\_histograms()

Get histograms for all antpols, summing over all interleaving Input:

antpol (int): Antpol number (zero-indexed)

#### **Returns:**

vals, hist vals (numpy array): histogram bin centers hist (numpy array): histogram data

#### get\_bit\_stats()

Get the mean, RMS, and powers of all ADCs Returns:

means, powers, rmss. Each is a numpy array with one entry per input.

#### get\_histogram(input, sum\_cores=True)

Get a histogram for an ADC input. Inputs:

input (int): ADC input from which to get data. sum\_cores (Boolean): If True, compute one histogram from both A & B ADC cores. If False, compute separate histograms.

#### **Returns:**

#### If sum cores is True:

vals, hist vals (numpy array): histogram bin centers hist (numpy array): histogram data

#### If sum cores is False:

vals, hist\_a, hist\_b vals (numpy array): histogram bin centers hist\_a (numpy array): histogram
data for "A" cores hist\_b (numpy array): histogram data for "B" cores

#### get\_power\_spectra (stream, acc\_len=1)

Perform a software FFT of samples from *antenna*. Accumulate power from *acc\_len* snapshots. Returns power spectrum as numpy array

#### get\_status()

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. flags\_dict is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

```
initialize(read only=False)
          Switch to ADCs. Begin computing stats.
     show_histogram_plot()
          A helper method for plotting multiple histograms without importing your own pyplot. eg.
              for i in range(Input.n_streams): Input.plot_histogram(i)
              Input.show_histogram_plot()
     use_adc (stream=None)
          Switch input to ADC. Inputs:
              stream (int): Which stream to switch. If None, switch all.
     use noise(stream=None)
          Switch input to internal noise source. Inputs:
              stream (int): Which stream to switch. If None, switch all.
     use_zero (stream=None)
          Switch input to zeros. Inputs:
              stream (int): Which stream to switch. If None, switch all.
2.2.5 Noise Generator Control
2.2.6 Delay Control
class lwa_f.blocks.delay.Delay(host, name, n_streams=64, logger=None)
     Instantiate a control interface for a Delay block.
          Parameters
                • host (casperfpga.CasperFpga) - CasperFpga interface for host.
                • name (str) - Name of block in Simulink hierarchy.
                • logger (logging.Logger) - Logger instance to which log messages should be emit-
                • n_streams (int) - Number of independent streams which may be delayed
     MIN_DELAY = 5
          minimum delay allowed
     get delay(stream)
          Get the current delay for a given input.
              Parameters stream (int) – Which ADC input index to query
              Returns Currently loaded delay, in ADC samples
              Return type int
     get_max_delay()
          Query the firmware to get the maximum delay it supports.
```

Returns Maximum supported delay, in ADC samples

Return type int

#### get\_status()

Get status and error flag dictionaries.

Status keys:

- delay<n>: Currently loaded delay for ADC input index n.
- max\_delay: The maximum delay supported by the firmware.
- min\_delay: The minimum delay supported by the firmware.

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. flags\_dict is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

#### initialize(read\_only=False)

Initialize all delays.

**Parameters read\_only** (bool) - If True, do nothing. If False, initialize all delays to the minimum allowed value.

```
set_delay (stream, delay)
```

Set the delay for a given input stream.

#### **Parameters**

- **stream** (*int*) ADC stream index to which delay should be applied.
- **delay** (*int*) Number of ADC clock cycles delay to load.

#### 2.2.7 PFB Control

class lwa\_f.blocks.pfb.Pfb (host, name, logger=None)

#### get\_status()

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. flags\_dict is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

#### initialize (read\_only=False)

Individual blocks should override this method to configure themselves appropriately

**Parameters read\_only** (bool) – If False, initialize blocks in a way that might change the configuration of running hardware. If True, read runtime info from blocks, but don't change anything.

#### 2.2.8 Auto-correlation Control

Instantiate a control interface for an Auto-Correlation block.

#### **Parameters**

- host (casperfpga. CasperFpga) CasperFpga interface for host.
- name (str) Name of block in Simulink hierarchy.
- logger (logging.Logger) Logger instance to which log messages should be emitted.
- acc\_len (int) Accumulation length initialization value, in spectra.
- **n\_chans** (*int*) Number of frequency channel.
- **n\_pols** (*int*) Number of individual data streams.
- n\_parallel\_streams (int) Number of streams processed by the firmware module in parallel.
- **n\_cores** (*int*) Number of accumulation cores in firmware design.
- **use\_mux** (bool) If True, only one core is instantiated and a multiplexer is used to switch different inputs into it. If False, multiple cores are instantiated simultaneously in firmware.

#### get\_acc\_len()

Get the currently loaded accumulation length in units of spectra.

**Returns** Current accumulation length

Return type int

#### get\_new\_spectra(core=0)

Get a new average power spectra.

**Parameters** core (int) – If using multiplexing, read data for this core. If not using multiplexing, read data from all cores.

**Returns** Float32 array of dimensions [POLARIZATION, FREQUENCY CHANNEL] containing autocorrelations with accumulation length divided out.

**Return type** numpy.array

#### get\_status()

Get status and error flag dictionaries.

Status keys:

• acc\_len: Currently loaded accumulation length

**return** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs. flags\_dict is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary are as defined in *error\_levels.py* and indicate that values in the status dictionary are outside normal ranges.

#### initialize(read\_only=False)

Initialize the block, setting (or reading) the accumulation length.

**Parameters read\_only** (bool) – If False, set the accumulation length to the value provided when this block was instantiated. If True, use whatever accumulation length is currently loaded.

#### plot\_spectra (core=0, db=True, show=True)

Plot the spectra of all polarizations in a single core, with accumulation length divided out

#### **Parameters**

- core (int) If using multiplexing, read data for this core. If not using multiplexing, read data from all cores.
- **db** (bool) If True, plot 10log10(power). Else, plot linear.
- **show** (bool) If True, call matplotlib's *show* after plotting

Returns matplotlib. Figure

```
set_acc_len (acc_len)
```

Set the number of spectra to accumulate.

**Parameters** acc\_len (int) – Number of spectra to accumulate

#### 2.2.9 Correlation Control

```
class lwa_f.snap2_fengine.Snap2Fengine(host, logger=None)
```

**configure** output (base ant, n chans per packet, chans, ips, ports=None, ants=None)

#### 2.2.10 Post-FFT Test Vector Control

class lwa\_f.blocks.eqtvg.EqTvg(host, name, n\_streams=64, n\_chans=4096, logger=None)

#### get status()

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. flags\_dict is a dictionary with all, or a sub-set, of the keys in *status dict*. The values held in this dictionary should be as defined in *error levels.py*.

#### initialize(read only=False)

Individual blocks should override this method to configure themselves appropriately

**Parameters read\_only** (bool) – If False, initialize blocks in a way that might change the configuration of running hardware. If True, read runtime info from blocks, but don't change anything.

#### read\_stream\_tvg(stream)

Read the test vector loaded to stream number stream.

stream [int] Index of stream from which test vectors should be read.

**tv** [numpy.Array] Test vector array.

#### write const per stream()

Write a constant to all the channels of a stream, with stream i taking the value i

#### write freq ramp()

Write a frequency ramp to the test vector that is repeated for all antennas.

#### write\_stream\_tvg(stream, test\_vector)

Write a test vector tv to stream number stream.

stream [int] Index of stream to which test vectors should be loaded

**test\_vector** [numpy.Array] Test vector array, with *self.n\_chans* elements

## 2.2.11 Equalization Control

```
class lwa_f.blocks.eq.Eq(host, name, n_streams=64, n_coeffs=512, logger=None)
```

#### clip\_count()

Get the total number of times any samples have clipped, since last sync.

#### get coeffs(stream)

Get the coefficients currently loaded. Reads the actual coefficients from the board. Inputs:

stream (int): Stream index to query

**Returns** numpy array of *self.n\_coeffs* coefficients currently being applied to this stream.

#### get\_status()

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. flags\_dict is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

#### initialize(read\_only=False)

Initialize block, setting coefficients to some nominally sane value. Currently, this is 100.0

#### set\_coeffs (stream, coeffs)

Set the coefficients for a data stream. Clipping and saturation will be applied before loading.

Inputs stream (int): Which stream to manipulate coeffs (list or numpy array): Coefficients to load.

#### 2.2.12 Channel Selection Control

#### 2.2.13 Packetization Control

```
class lwa_f.blocks.packetizer.Packetizer(host, name, n_chans=4096, n_pols=64, sample rate mhz=200.0.logger=None)
```

The packetizer block allows dynamic definition of packet sizes and contents. In firmware, it is a simple block which allows insertion of header entries and EOFs at any point in the incoming data stream. It is up to the user to configure this block such that it behaves in a reasonable manner – i.e.

- Output data rate does not overflow the downstream Ethernet core
- Packets have a reasonable size
- EOFs and headers are correctly placed.

```
get_packet_info(n_pkt_chans, occupation=0.95, chan_block_size=8)
```

Get the packet boundaries for packets with payload sizes  $n\_bytes$ .

**n\_pkt\_chans** [int] The number of channels per packet.

**occupation** [float] The maximum allowed throughput capacity of the underlying link. The calculation does not include application or protocol overhead, so must necessarily be < 1.

**chan\_block\_size** [int] The granularity with which we can start packets. I.e., packets must start on an n\*`chan block` boundary.

packet\_starts, packet\_payloads, channel\_indices

**packet\_starts** [list of ints] The word indexes where packets start – i.e., where headers should be written. For example, a value [0, 1024, 2048, ...] indicates that headers should be written into underlying brams at addresses 0, 1024, etc.

**packet\_payloads** [list of range()] The range of indices where this packet's payload falls. Eg: [range(1,257), range(1025,1281), range(2049,2305), ... etc] These indices should be marked valid, and the last given an EOF.

**channel\_indices** [list of range()] The range of channel indices this packet will send. Eg: [range(1,129), range(1025,1153), range(2049,2177), ... etc] Channels to be sent should be re-indexed so that they fall into these ranges.

Write the packetizer configuration BRAMs with appropriate entries.

packet\_starts [list of ints] Word-indices which are the first entry of a packet and should be populated
with headers (see get\_packet\_info())

packet\_payloads [list of range()s] Word-indices which are data payloads, and should be mared as valid
 (see get\_packet\_info())

**channel indices** [list of ints] Header entries for the channel field of each packet to be sent

ant\_indices [list of ints] Header entries for the antenna field of each packet to be sent

**dest\_ips** [list of str] IP addresses for each packet to be sent.

**dest\_ports** [list of int] UDP destination ports for each packet to be sent.

print [bool] If True, print config for debugging

All parameters should have identical lengths.

# 2.2.14 Ethernet Output Control

class lwa\_f.blocks.eth.Eth(host, name, logger=None)

#### add\_arp\_entry(ip, mac)

Set a single arp entry.

#### get status()

Get a dictionary of status values, with optional warning of error flags. To be overridden by individual blocks

**Returns** (status\_dict, flags\_dict) tuple. *status\_dict* is a dictionary of status key-value pairs, defined on a per-block basis. flags\_dict is a dictionary with all, or a sub-set, of the keys in *status\_dict*. The values held in this dictionary should be as defined in *error\_levels.py*.

```
initialize (read_only=False)
```

Individual blocks should override this method to configure themselves appropriately

**Parameters read\_only** (bool) – If False, initialize blocks in a way that might change the configuration of running hardware. If True, read runtime info from blocks, but don't change anything.

#### set\_arp\_table (macs)

Set the ARP table with a list of MAC addresses. The list, *macs*, is passed such that the zeroth element is the MAC address of the device with IP XXX.XXX.XXX.0, and element N is the MAC address of the device with IP XXX.XXX.XXX.N

## 2.3 etcd Interface

The etcd F-Engine interface provides a mechanism to control multiple SNAP2 boards running F-Engine firmware via the passing of messages through an etcd key-value store.

In order to use the etcd control interface, a daemon Snap2FengineEtcdClient instance is required to be running on a server with network access to the SNAP2 hardware being controlled.

For an F-Engine running on a SNAP2 hostname, there are three relevant etcd key paths.

The command key is:

/cmd/snap/<hostname>/command

Writing messages to this key results in the execution of Snap2Fengine command methods.

Each command written to the command key will elicit a response published to the key:

/resp/snap/<hostname>/response

The response message will indicate the success of failure of the command, and may contain a command-dependent data payload. For example, a spectra, or snapshot of ADC samples.

In addition to the Command/Response control protocol, general telemetry relating to pipeline element blockname can be read from the keys beneath the path:

/mon/snap/<hostname>/<blockname>

Such keys are indended to be continuously updated on a ~1 second time cadence, and contain low data-volume status information. For example, FPGA temperature, ADC RMS, number of transmitted Ethernet packets, and similar.

The Command/Response protocol is designed to be a simple interface to the underlying Snap2Fengine control class. It will naturally extend as the control class functionality is expanded.

A simple example of a control client is implemented in the Snap2FengineEtcdControl class, which is used for internal testing.

Commands sent to the command key are JSON-encoded dictionaries, and should have the following fields:

Field	Туре	Description	
se-	integer	A unique integer associated with this command, used to identify the command's re-	
quence_id		sponse	
timestamp	float	The UNIX time when this command was issued	
command	string	Command Name	
block	string	Firmware block name to which command applies	
kwargs	dictio-	Dictionary of arguments required by the block.command method	
	nary		

Allowed values for "block" are any of the keys in the Snap2Fengine blocks attribute. I.e.:

```
from lwa_f import snap2_fengine
f = snap2_fengine.Snap2Fengine('snap2-rev2-11')
for block in sorted(f.blocks.keys()): print(block)
adc
autocorr
corr
delay
eq
eq_tvg
eth
input
noise
packetizer
pfb
reorder
sync
```

Allowed values for "command" are any of the methods which can be called against Snap2Fengine. blocks[block]. For example, for the delay block, allowed commands are:

```
• get_max_delay
```

- set\_delay
- get\_delay
- initialize
- get\_status

All blocks are instances of the generic Block class, and thus it is also possible to call parent class methods such as read\_uint and write\_uint. These directly manipulate FPGA registers, and should be used with caution.

The "kwargs" field should contain any arguments required by the command method being called. For example, the Fengine delay block's set\_delay method requires a stream argument (to select which of the 64 SNAP2 data streams is being manipulated) and a delay argument (to set the delay for this stream).

As such, in order to set the delay of data stream 5 to 100 adc samples, a command should be issued with:

Field	Value	
block	"delay"	
command	"set_delay"	
kwargs	{"stream": 5, "delay": 100}	

An example of a valid command JSON string, issued with the above parameters at UNIX time 1618060712.60 and with sequence\_id=1 is:

```
'{"block": "delay", "timestamp": 1618060712.6, "kwargs": {"delay": 100, "stream": 5}, "command": "set_delay", "sequence_id": 1}'
```

Consult the Snap2Fengine API details for a list of commands and their arguments.

Every command sent elicits the writing of JSON-encoded dictionary to the response key. This dictionary has the following fields:

2.3. etcd Interface 17

Field	Type	Description
se-	integer	An integer matching the sequence_id field of the command string to which this is a response
quenc	e_id	
times-	- float	The UNIX time when this response was issued
tamp		
sta-	string	The string "normal" if the corresponding command was processed without error, or "error" if it
tus		was not.
re-	comman	d-The response of the command method, as determined by the command API. If a method would
spons	sponse dependentusually return a numpy array, when using the etcd interface the response will be a list. In	
		event that the status field is "error", The response field will contain an error message string

Not all Snap2Fengine methods return values, in whice case the response field is null. The previous command example (setting a delay) results in the underlying API call Snap2Fengine.blocks['delay'].set\_delay(5, 100) which returns None. The response to the example command (assuming processing the command took 0.2 milliseconds) is thus:

Field	Value
sequence_id	1
``timestamp` `	1618060712.8
status	"normal"
response	null

#### or, in JSON-encoded form:

```
'{"sequence_id": 1, "timestamp": 1618060712.8, "status": "normal", "response": null}'
```

If the response status field is "error", common response error messages, and their meanings are:

"JSON decode er-	Command string could not be JSON-decoded.		
ror"			
"Sequence ID not in-	Sequence ID was not provided in the command string or decoded to a non-integer value.		
teger"			
"Bad command for-	Received command did not comply with formatting specifications. E.g. was missing a		
mat"	required field such as block or command.		
"Command invalid"	Received command doesn't exist in the Snap2Fengine API, or is prohibited for etcd		
	access.		
"Wrong block"	block field of the command decoded to a block which doesn't exist.		
"Command argu-	kwargs key contained missing, or unexpected keys.		
ments invalid"			
"Command failed"	'Command failed" The underlying Snap2Fengine API call raised an exception.		

In the event that a command fails, more information is available in the Snap2FengineEtcdClient daemon logs.

autocorr/acc_len	int	Accumulation length, in spectra, of the internal autocorrelation module.
corr/acc_len	int	Accumulation length, in spectra, of the internal correlation module.
delay/n/delay	int	Delay of each of the n data streams.
delay/maxdelay	int	The maximum delay supported by the firmware.
eq/binary_point	int	The position of the EQ coefficient binary point
eq/width	int	The bit width of the EQ coefficients
eq/clip_count	int	The number of clips when requantizing spectra to 4-bit. This counter resets every [TODO: w

Table 2.1 – continued from previous page

		p p
autocorr/acc_len	int	Accumulation length, in spectra, of the internal autocorrelation module.
eq/n/coefficients	list (int)	The currently loaded coefficients, in integer form (i.e., interpretted with all bits above the bin
eq_tvg/tvg_enabled	bool	True if the post-FFT test vector generator is enabled. False otherwise.
eth/tx_ctr	int	Running count of number of packets transmitted.
eth/tx_err	int	Running count of number of packet errors detected.
eth/tx_full	int	Running count of number of transmission buffer overflow events.
eth/tx_vld	int	Running count of number of 256-bit words transmitted.
feng/flash_firmware	string	The current .fpg bitstream file stored in flash memory
feng/flash_firmware_md5	int	The MD5 checksum of the .fpg bitstream stored in flash
feng/host	string	The hostname of the SNAP2 board
feng/programmed	bool	True if the board appears to be running DSP firmware. False otherwise.
feng/serial	string	A notional "serial number" of this hardware. Not yet implemented.
feng/sw_version	string	The software version of the lwa_f python library currently in use
feng/sys_mon	string	"reporting" if the current firmware has a working system monitor module. "not reporting" if
feng/temp	float	FPGA junction temperature, in degrees C, reported by system monitor (if available)
feng/vccaux	float	Voltage of the VCCAUX FPGA power rail reported by system monitor (if available)
feng/vccbram	float	Voltage of the VCCBRAM FPGA power rail reported by system monitor (if available)
feng/vccint	float	Voltage of the VCCINT FPGA power rail reported by system monitor (if available)
input/n/mean	float	Mean of ADC sample values for input ADC n.
input/n/rms	float	RMS of ADC sample values for input ADC n.
input/n/power	float	Mean of squares of ADC sample values for input ADC n.
input/n/switch_position	string	Switch position for input data stream n. noise for internal noise generators, add for analog
noise/noise_core00_seed	int	Seed value for internal noise generator 0.
noise/noise_core01_seed	int	Seed value for internal noise generator 1.
noise/noise_core02_seed	int	Seed value for internal noise generator 2.
noise/n/output_assignment	int	Noise source (0 - 5) currently assigned to data stream n.
pfb/fft_shift	int	Currently loaded FFT shift schedule.
pfb/overflow_count	int	Running count of FFT overflow events.
sync/ext_count	int	Running count of number of external sync pulses received since FPGA was programmed.
sync/int_count	int	Running count of number of internal sync pulses received since FPGA was programmed.
sync/period_fpga_clks	int	Detected period of external sync pulses in units of FPGA clock cycles.
sync/uptime_secs	int	Number of seconds since FPGA was last programmed

2.3. etcd Interface

# **CHAPTER**

# **THREE**

# **INDICES AND TABLES**

- genindex
- modindex
- search

# **INDEX**

A	<pre>get_snapshot_interleaved()</pre>
Adc (class in lwa_f.blocks.adc), 7 add_arp_entry() (lwa_f.blocks.eth.Eth method), 15 AutoCorr (class in lwa_f.blocks.autocorr), 12	(lwa_f.blocks.adc.Adc method), 7 get_status() (lwa_f.blocks.autocorr.AutoCorr method), 12
С	get_status() (lwa_f.blocks.delay.Delay method), 6, 10
<pre>calibrate() (lwa_f.blocks.adc.Adc method), 7 clip_count() (lwa_f.blocks.eq.Eq method), 14 configure_output()</pre>	get_status() (lwa_f.blocks.eq.Eq method), 14 get_status() (lwa_f.blocks.eqtvg.EqTvg method), 13 get_status() (lwa_f.blocks.eth.Eth method), 15 get_status() (lwa_f.blocks.input.Input method), 9 get_status() (lwa_f.blocks.pfb.Pfb method), 11
D	I
Delay (class in lwa_f.blocks.delay), 6, 10	initialize() (lwa_f.blocks.adc.Adc method), 8
Eq(class in lwa_f.blocks.eq), 14 EqTvg (class in lwa_f.blocks.eqtvg), 13 Eth (class in lwa_f.blocks.eth), 15  G get_acc_len() (lwa_f.blocks.autocorr.AutoCorr method), 12 get_all_histograms() (lwa_f.blocks.input.Input method), 9 get_bit_stats() (lwa_f.blocks.input.Input method), 9 get_coeffs() (lwa_f.blocks.eq.Eq method), 14 get_delay() (lwa_f.blocks.delay.Delay method), 6,	<pre>initialize() (lwa_f.blocks.autocorr.AutoCorr</pre>
get_histogram() (lwa_f.blocks.input.Input method), get_max_delay() (lwa_f.blocks.delay.Delay method), 6, 10 get_new_spectra() (lwa_f.blocks.autocorr.AutoCorr method), 12.	Packetizer (class in lwa_f.blocks.packetizer), 14 Pfb (class in lwa_f.blocks.pfb), 11 plot_spectra() (lwa_f.blocks.autocorr.AutoCorr
<pre>get_packet_info()</pre>	R
<pre>(lwa_f.blocks.packetizer.Packetizer method), 14 get_power_spectra() (lwa_f.blocks.input.Input</pre>	read_stream_tvg() (lwa_f.blocks.eqtvg.EqTvg method), 13 reset() (lwa_f.blocks.adc.Adc method), 8

# S

```
set acc len()
                     (lwa_f.blocks.autocorr.AutoCorr
        method), 13
set_arp_table() (lwa_f.blocks.eth.Eth method), 16
set_coeffs() (lwa_f.blocks.eq.Eq method), 14
set_delay() (lwa_f.blocks.delay.Delay method), 7,
        11
set_delays() (lwa_f.blocks.adc.Adc method), 8
show_histogram_plot() (lwa_f.blocks.input.Input
        method), 10
Snap2Fengine (class in lwa_f.snap2_fengine), 6, 13
sync() (lwa_f.blocks.adc.Adc method), 9
U
use_adc() (lwa_f.blocks.input.Input method), 10
use_noise()(lwa_f.blocks.input.Input method), 10
use_zero() (lwa_f.blocks.input.Input method), 10
W
write_config() (lwa_f.blocks.packetizer.Packetizer
        method), 15
write_const_per_stream()
        (lwa_f.blocks.eqtvg.EqTvg method), 13
write_freq_ramp()
                          (lwa_f.blocks.eqtvg.EqTvg
        method), 13
write_stream_tvg()
                          (lwa_f.blocks.eqtvg.EqTvg
```

method), 14

24 Index